
Coherent PDF Command Line Tools





For bug reports, feature requests and comments, email

contact@coherentgraphics.co.uk

©2022 Coherent Graphics Limited. All rights reserved. ISBN 978-0957671140

Adobe, Acrobat, and Adobe PDF are registered trademarks of Adobe Systems Incorporated. Windows, Powerpoint and Excel are registered trademarks of Microsoft Corporation.

Quickstart Examples

A sampling of just a few of the facilities provided by the Coherent PDF Command Line Tools.

Basic Usage

cpdf in.pdf 1-3,6 -o out.pdf

Read in.pdf, select pages 1, 2, 3 and 6, and write those pages to out.pdf.

cpdf in.pdf even -o out.pdf

Select the even pages (2, 4, 6...) from in.pdf and write those pages to out.pdf.

Using AND to perform several operations in order, here merging two files together and adding a copyright stamp to every page.

```
cpdf -args control.txt
```

Read control.txt and use its contents as the command line arguments for cpdf.

Merging and Splitting

cpdf -merge in.pdf in2.pdf -o out.pdf

Merge in.pdf and in2.pdf into one document, writing to out.pdf.

cpdf -split in.pdf -o Chunk%%%.pdf -chunk 10

Split in.pdf into ten-page chunks, writing them to Chunk001.pdf, Chunk002.pdf etc.

```
cpdf -split-bookmarks 0 in.pdf -o @N.pdf
```

Split in.pdf on bookmark boundaries, writing each to a file whose name is the bookmark label.

Pages

```
cpdf -scale-page "2 2" in.pdf -o out.pdf
```

Scale both the dimensions and contents of in.pdf by a factor of two in x and y directions.

cpdf -scale-to-fit usletterportrait in.pdf -o out.pdf

Scale the pages in in.pdf to fit the US Letter page size, writing to out.pdf

cpdf -shift "26pt 18mm" in.pdf -o out.pdf

Shift the contents of the page by 26 pts in the x direction, and 18 millimetres in the y direction, writing to out.pdf

cpdf -rotate-contents 90 in.pdf -o out.pdf

Rotate the contents of the pages in in.pdf by ninety degrees and write to out.pdf.

cpdf -crop "0 0 600pt 400pt" in.pdf -o out.pdf

Crop the pages in in.pdf to a 600 pts by 400 pts rectangle.

Encryption and Decryption

cpdf -encrypt 128bit fred joe in.pdf -o out.pdf

Encrypt in.pdf using 128bit PDF encryption using the owner password fred and the user password joe and writing the encrypted file to out.pdf

```
cpdf -decrypt in.pdf owner=fred -o out.pdf
```

Decrypt in.pdf using the owner password, writing to out.pdf.

Compression

cpdf -compress in.pdf -o out.pdf

Compress the data streams in in.pdf, writing the result to out.pdf.

cpdf -decompress in.pdf -o out.pdf

Decompress the data streams in in.pdf, writing to out.pdf.

```
cpdf -squeeze in.pdf -o out.pdf
```

Squeeze in.pdf, writing to out.pdf. Squeezing rearranges the structure of the PDF file to save space.

Bookmarks

cpdf -list-bookmarks in.pdf

List the bookmarks in in.pdf.

cpdf -add-bookmarks bookmarks.txt in.pdf -o out.pdf

Add bookmarks in the same form from a prepared file bookmarks.txt to in.pdf, writing to out.pdf.

Presentations

```
cpdf -presentation in.pdf 2-end -trans Split -duration 10
-o out.pdf
```

Use the Split style to build a presentation from the PDF in.pdf, each slide staying 10 seconds on screen unless manually advanced. The first page, being a title does not move on automatically, and has no transition effect.

Logos, Watermarks and Stamps

cpdf -stamp-on watermark.pdf in.pdf -o out.pdf

Stamp the file watermark.pdf on to each page of in.pdf, writing the result to out.pdf.

```
cpdf -topleft 10 -font Courier
-add-text "Page %Page\nDate %d-%m-%Y" in.pdf -o out.pdf
```

Add a page number and date to all the pages in in.pdf using the Courier font, writing to out.pdf.

Multipage Facilities

cpdf -twoup-stack in.pdf -o out.pdf

Two up impose the file in.pdf, writing to out.pdf.

cpdf -pad-after in.pdf 1,3,4 -o out.pdf

Add extra blank pages after pages one, three and four of a document.

Annotations

cpdf -list-annotations in.pdf

List the annotations in a file in.pdf to standard output.

cpdf -copy-annotations from.pdf in.pdf -o out.pdf

Copy the annotations from from.pdf to in.pdf, writing to out.pdf.

Document Information and Metadata

cpdf -set-title "The New Title" in.pdf -o out.pdf

Set the document title of in.pdf. writing to out.pdf.

```
cpdf -hide-toolbar true in.pdf -o out.pdf
```

Set the document in.pdf to open with the PDF Viewer's toolbar hidden, writing to out.pdf.

```
cpdf -set-metadata metadata.xml in.pdf -o out.pdf
```

Set the metadata in a PDF in.pdf to the contents of the file metadata.xml, and write the output to out.pdf.

cpdf -set-page-layout TwoColumnRight in.pdf -o out.pdf

Set the document in.pdf to open in PDF Viewer showing two columns of pages, starting on the right, putting the result in out.pdf.

```
cpdf -set-page-mode FullScreen in.pdf -o out.pdf
```

Set the document in.pdf to open in PDF Viewer in full screen mode, putting the result in out.pdf.

File Attachments

```
cpdf -attach-file sheet.xls in.pdf -o out.pdf
```

Attach the file sheet.xls to in.pdf, writing to out.pdf.

cpdf -remove-files in.pdf -o out.pdf

Remove any attachments from in.pdf, writing to out.pdf.

Working with Images

cpdf -image-resolution 600 in.pdf

Identify and list any image used at less than 600dpi.

cpdf -extract-images in.pdf -im /usr/bin/magick -o output/%%%

Extract images from in.pdf to directory output (with the help of imagemagick).

Fonts

cpdf -list-fonts in.pdf

List the fonts in use, and what pages they are used on.

cpdf -gs /usr/bin/gs -embed-missing-fonts in.pdf -o out.pdf

Embed missing fonts (with the help of Ghostscript).

PDF and JSON

```
cpdf in.pdf -output-json -output-json-parse-content-streams
-o out.json
```

Write the PDF in JSON format to the given file, parsing its content streams into individual JSON objects too.

Optional Content Groups

```
cpdf -ocg-list in.pdf
```

List the optional content groups by name.

```
cpdf -ocg-coalesce-on-name in.pdf -o out.pdf
```

Coalesce optional content groups after merging or stamping two files with OCGs with like names.

Miscellaneous

```
cpdf -blacktext in.pdf -o out.pdf
```

Blacken all the text in in.pdf, writing to out.pdf.

```
cpdf -thinlines 2pt in.pdf -o out.pdf
```

Make sure all lines in in.pdf are at least 2 pts wide, writing to out.pdf.

Contents

1	Basic Usage 1			
	1.1	Documentation		
	1.2	Input and Output Files		
	1.3	Input Ranges		
	1.4	Working with Encrypted Documents		
	1.5	Standard Input and Standard Output		
	1.6	Doing Several Things at Once with AND		
	1.7	Units		
	1.8	Setting the Producer and Creator		
	1.9	PDF Version Numbers		
	1.10	File IDs		
	1.11	Linearization		
	1.12	Object Streams		
	1.13	Malformed Files		
	1.14	Error Handling		
	1.15	Control Files		
	1.16	String Arguments		
	1.17	Text Encodings 1		
	1.18	Font Embedding		
2	Mer	ging and Splitting 1		
	2.1	Merging		
	2.2	Splitting 12		
	2.3	Splitting on Bookmarks		
	2.4	Encrypting with Split and Split Bookmarks 1		
3	Page	es 1		
	3.1	Page Sizes 10		
	3.2	Scale Pages		
	3.3	Shift Page Contents		
	3.4	Rotating Pages		
	3.5	Flipping Pages		
	3.6	Boxes and Cropping		
	3.7	Showing Boxes and Printer's Marks 19		

4	Encr	yption and Decryption	21				
	4.1	Introduction	21				
	4.2	Encrypting a Document	22				
	4.3	Decrypting a Document	22				
5	Com	Compression 23					
	5.1	I O	23				
	5.2	1 0	23				
	5.3	Squeezing a Document	24				
6	Bool	kmarks	25				
	6.1	List Bookmarks	25				
		6.1.1 Destinations	26				
	6.2	Remove Bookmarks	27				
	6.3	Add Bookmarks	27				
	6.4	Opening bookmarks	28				
	6.5	Making a Table of Contents	28				
7	Pres	entations	31				
8 Watermarks and Stamps							
	8.1	Add a Watermark or Logo	33				
	8.2	Stamp Text, Dates and Times.	34				
		8.2.1 Page Numbers	34				
		•	35				
		8.2.3 Bates Numbers	35				
		8.2.4 Position	36				
		8.2.5 Font and Size	36				
		8.2.6 Colors	37				
		8.2.7 Outline Text	38				
		8.2.8 Multi-line Text	38				
		8.2.9 Special Characters	39				
	8.3	Stamping Graphics	39				
	8.4	Low-level facilities	39				
9	Mul	tipage Facilities	41				
	9.1		41				
	9.2		42				
10	Ann	otations	45				
			45				
			45				
			46				

11 Document Information and Metadata	47
11.1 Reading Document Information	
11.2 Setting Document Information	49
11.3 XMP Metadata	
11.4 Upon Opening a Document	50
11.4.1 Page Layout	50
11.4.2 Page Mode	51
11.4.3 Display Options	52
11.5 Page Labels	52
12 File Attachments	55
12.1 Adding Attachments	
12.2 Listing Attachments	
12.3 Removing Attachments	
12.4 Dumping Attachments to File	56
13 Working with Images	57
13.1 Extracting images	
13.2 Detecting Low-resolution Images	
13.3 Removing an Image	
	50
14 Fonts	59
14.1 Listing Fonts	59
14.2 Listing characters in a font	60
14.3 Copying Fonts	
14.4 Removing Fonts	
14.5 Missing Fonts	
15 PDF and JSON	63
16 Optional Content Groups	65
17 Creating New PDFs	67
17.1 A new blank PDF	
17.2 Convert a text file to PDF	
18 Miscellaneous	69
18.1 Draft Documents	69
18.2 Blackening Text, Lines and Fills	70
18.3 Hairline Removal	70
18.4 Garbage Collection	71
18.5 Change PDF Version Number	71
18.6 Copy ID	71
18.7 Remove ID	71
18.8 List Spot Colours	72
18.9 PDF Dictionary Entries	72
18.10Removing Clipping	73

A	Dates	75
	A.1 PDF Date Format	75
	A.2 XMP Metadata Date Format	76

Typographical Conventions

Command lines to be typed are shown in typewriter font in a box. For example:

cpdf in.pdf -o out.pdf

When describing the general form of a command, rather than a particular example, square brackets [] are used to enclose optional parts, and angled braces <> to enclose general descriptions which may be substituted for particular instances. For example,

cpdf <operation> in.pdf [<range>] -o out.pdf

describes a command line which requires an operation and, optionally, a range. An exception is that we use in.pdf and out.pdf instead of <input file> and <output file> to reduce verbosity. Under Microsoft Windows, type cpdf.exe instead of cpdf.

Chapter 1

Basic Usage

```
-help
                       --help
                                               -version
-0
                       -i
                                              -idir <directory>
                     -decrypt-force
-recrypt
                                             -stdout
                    -stdin-user <password> -stdin-owner <password>
-creator <text> -change-id
-stdin
-producer <text>
                     -cpdflin <filename>
-1
                                             -keep-l
-no-preserve-objstm -create-objstm
                                              -control <filename>
-args <filename>
                      -utf8
                                              -stripped
                      -no-embed-font
-raw
                                              -qs
-gs-malformed
                       -gs-malformed-force
                                             -gs-quiet
-error-on-malformed
```

The Coherent PDF tools provide a wide range of facilities for modifying PDF files created by other means. There is a single command-line program cpdf (cpdf.exe under Microsoft Windows). The rest of this manual describes the options that may be given to this program.

1.1 Documentation

The operation <code>-help / --help</code> prints each operation and option together with a short description. The operation <code>-version</code> prints the cpdf version string.

1.2 Input and Output Files

The typical pattern for usage is

cpdf [<operation>] <input file(s)> -o <output file>

and the simplest concrete example, assuming the existence of a file in.pdf is:

cpdf in.pdf -o out.pdf

which copies in.pdf to out.pdf. The input and output may be the same file. Of course, we should like to do more interesting things to the PDF file than that!

Files on the command line are distinguished from other input by their containing a period. If an input file does not contain a period, it should be preceded by -i. For example:

cpdf -i in -o out.pdf

A whole directory of files may be added (where a command supports multiple files) by using the -idir option:

cpdf -merge -idir myfiles -o out.pdf

The files in the directory myfiles are considered in alphabetical order. They must all be PDF files. If the names of the files are numeric, leading zeroes will be required for the order to be correct (e.g 001.pdf, 002.pdf etc).

To restrict cpdf to files ending in .pdf (in upper or lower or mixed case) add the option -idir-only-pdfs *before* -idir:

cpdf -merge -idir-only-pdfs -idir myfiles -o out.pdf

1.3 Input Ranges

An *input range* may be specified after each input file. This is treated differently by each operation. For instance

cpdf in.pdf 2-5 -o out.pdf

extracts pages two, three, four and five from in.pdf, writing the result to out.pdf, assuming that in.pdf contains at least five pages. Here are the rules for building input ranges:

- A dash (-) defines ranges, e.g. 1–5 or 6–3.
- A comma (,) allows one to specify several ranges, e.g. 1–2, 4–5.
- The word end represents the last page number.
- The words odd and even can be used in place of or at the end of a page range to restrict to just the odd or even pages.

- The words portrait and landscape can be used in place of or at the end of a page range to restrict to just those pages which are portrait or landscape. Note that the meaning of "portrait" and "landscape" does not take account of any viewing rotation in place (use -upright first, if required). A page with equal width and height is considered neither portrait nor landscape.
- The word reverse is the same as end-1.
- The word all is the same as 1-end.
- A range must contain no spaces.
- A tilde (~) defines a page number counting from the end of the document rather than the beginning. Page ~1 is the last page, ~2 the penultimate page etc.
- Prepending NOT to a whole page range inverts it.
- Prepending <n>DUP to a whole page range duplicates each page of the range <n> times.

For example:

```
cpdf in.pdf 1,2,7-end -o out.pdf
Remove pages three, four, five and six from a document.
  cpdf in.pdf 1-16odd -o out.pdf
Extract the odd pages 1,3,...,13,15.
  cpdf in.pdf landscape -rotate 90 -o out.pdf
Rotate all landscape pages by ninety degrees.
  cpdf in.pdf 1, all -o out.pdf
Duplicate the front page of a document, perhaps as a fax cover sheet.
  cpdf in.pdf ~3-~1 -o out.pdf
Extract the last three pages of a document, in order.
  cpdf in.pdf 2DUP1-10 -o out.pdf
```

Produce the pages 1,1,2,2,....10,10.

1.4 Working with Encrypted Documents

In order to perform many operations, encrypted input PDF files must be decrypted. Some require the owner password, some either the user or owner passwords. Either password is supplied by writing user=<password> or owner=<password> following each input file requiring it (before or after any range). The document will *not* be re-encrypted upon writing. For example:

```
cpdf in.pdf user=charles -info
cpdf in.pdf owner=fred reverse -o out.pdf
```

To re-encrypt the file with its existing encryption upon writing, which is required if only the user password was supplied, but allowed in any case, add the -recrypt option:

cpdf in.pdf user=charles reverse -recrypt -o out.pdf

The password required (owner or user) depends upon the operation being performed. Separate facilities are provided to decrypt and encrypt files (See Section 4).

When appropriate passwords are not available, the option <code>-decrypt-force</code> may be added to the command line to process the file regardless.

1.5 Standard Input and Standard Output

Thus far, we have assumed that the input PDF will be read from a file on disk, and the output written similarly. Often it's useful to be able to read input from stdin (Standard Input) or write output to stdout (Standard Output) instead. The typical use is to join several programs together into a *pipe*, passing data from one to the next without the use of intermediate files. Use -stdin to read from standard input, and -stdout to write to standard input, either to pipe data between multiple programs, or multiple invocations of the same program. For example, this sequence of commands (all typed on one line)

```
cpdf in.pdf reverse -stdout |
cpdf -stdin 1-5 -stdout |
cpdf -stdin reverse -o out.pdf
```

extracts the last five pages of in.pdf in the correct order, writing them to out.pdf. It does this by reversing the input, taking the first five pages and then reversing the result.

To supply passwords for a file from -stdin, use -stdin-owner <password> and/or -stdin-user <password>.

Using -stdout on the final command in the pipeline to output the PDF to screen is not recommended, since PDF files often contain compressed sections which are not screen-readable.

Several cpdf operations write to standard output by default (for example, listing fonts). A useful feature of the command line (not specific to cpdf) is the ability to redirect this output to a file. This is achieved with the > operator:

cpdf -info in.pdf > file.txt

Use the -info operation (See Section 11.1), redirecting the output to file.txt.

1.6 Doing Several Things at Once with AND

The keyword AND can be used to string together several commands in one. The advantage compared with using pipes is that the file need not be repeatedly parsed and written out, saving time.

To use AND, simply leave off the output specifier (e.g -0) of one command, and the input specifier (e.g filename) of the next. For instance:

```
cpdf -merge in.pdf in2.pdf AND -add-text "Label"
AND -merge in3.pdf -o out.pdf
```

Merge in.pdf and in2.pdf together, add text to both pages, append in3.pdf and write to out.pdf.

To specify the range for each section, use -range:

```
cpdf -merge in.pdf in2.pdf AND -range 2-4 -add-text "Label"
AND -merge in3.pdf -o out.pdf
```

1.7 Units

When measurements are given to cpdf, they are in points (1 point = 1/72 inch). They may optionally be followed by some letters to change the measurement. The following are supported:

- pt Points (72 points per inch). The default.
- cm Centimeters
- mm Millimeters
- in Inches

For example, one may write 14mm or 21.6in. In addition, the following letters stand, in some operations (-scale-page, -scale-to-fit, -scale-contents, -shift, -mediabox, -crop) for various page dimensions:

For example, we may write PMINX PMINY to stand for the coordinate of the lower left corner of the page.

Simple arithmetic may be performed using the words add, sub, mul and div to stand for addition, subtraction, multiplication and division. For example, one may write 14in sub 30pt or PMINX mul 2

1.8 Setting the Producer and Creator

The -producer and -creator options may be added to any cpdf command line to set the producer and/or creator of the PDF file. If the file was converted from another format, the *creator* is the program producing the original, the *producer* the program converting it to PDF.

PW	Page width
PH	Page height
PMINX	Page minimum x coordinate
PMINY	Page minimum y coordinate
PMAXX	Page maximum x coordinate
PMAXY	Page maximum y coordinate
CW	Crop box width
CH	Crop box height
CMINX	Crop box minimum x coordinate
CMINY	Crop box minimum y coordinate
CMAXX	Crop box maximum x coordinate
CMAXY	Crop box maximum y coordinate

```
cpdf -merge in.pdf in2.pdf -producer MyMerger -o out.pdf
```

Merge in.pdf and in2.pdf, setting the producer to MyMerger and writing the output to out.pdf.

1.9 PDF Version Numbers

When an operation which uses a part of the PDF standard which was introduced in a later version than that of the input file, the PDF version in the output file is set to the later version (most PDF viewers will try to load any PDF file, even if it is marked with a later version number). However, this automatic version changing may be suppressed with the <code>-keep-version</code> option. If you wish to manually alter the PDF version of a file, use the <code>-set-version</code> operation described in Section 18.5.

1.10 File IDs

PDF files contain an ID (consisting of two parts), used by some workflow systems to uniquely identify a file. To change the ID, behavior, use the -change-id operation. This will create a new ID for the output file.

```
cpdf -change-id in.pdf -o out.pdf
Write in.pdf to out.pdf, changing the ID.
```

1.11 Linearization

Linearized PDF is a version of the PDF format in which the data is held in a special manner to allow content to be fetched only when needed. This means viewing a multipage PDF over a

slow connection is more responsive. By default, cpdf does not linearize output files. To make it do so, add the -1 option to the command line, in addition to any other command being used. For example:

```
cpdf -l in.pdf -o out.pdf
```

Linearize the file in.pdf, writing to out.pdf.

This requires the existence of the external program <code>cpdflin</code> which is provided with commercial versions of <code>cpdf</code>. This must be installed as described in the installation documentation provided with your copy of <code>cpdf</code>. If you are unable to install <code>cpdflin</code>, you must use <code>-cpdflin</code> to let <code>cpdf</code> know where to find it:

```
cpdf.exe -cpdflin "C:\\cpdflin.exe" -l in.pdf -o out.pdf
```

```
Linearize the file in.pdf, writing to out.pdf.
```

In extremis, you may place cpdflin and its resources in the current working directory, though this is not recommended. For further help, refer to the installation instructions for your copy of cpdf.

To keep the existing linearization status of a file (produce linearized output if the input is linearized and the reverse), use -keep-1 instead of -1.

1.12 Object Streams

PDF 1.5 introduced a new mechanism for storing objects to save space: object streams. by default, cpdf will preserve object streams in input files, creating no more. To prevent the retention of existing object streams, use -no-preserve-objstm:

```
cpdf -no-preserve-objstm in.pdf -o out.pdf
```

Write the file in.pdf to out.pdf, removing any object streams.

To create new object streams if none exist, or augment the existing ones, use -create-objstm:

```
cpdf -create-objstm in.pdf -o out.pdf
```

Write the file in.pdf to out.pdf, preserving any existing object streams, and creating any new ones for new objects which have been added.

To create wholly new object streams, use both options together:

cpdf -create-objstm -no-preserve-objstm in.pdf -o out.pdf

Write the file in.pdf to out.pdf with wholly new object streams.

Files written with object streams will be set to PDF 1.5 or higher, unless -keep-version is used (see above).

1.13 Malformed Files

There are many malformed PDF files in existence, including many produced by otherwise-reputable applications. cpdf attempts to correct these problems silently.

Grossly malformed files will be reconstructed. The reconstruction progress is shown on stderr (Standard Error):

```
$cpdf in.pdf -o out.pdf
couldn't lex object number
Attempting to reconstruct the malformed pdf in.pdf...
Read 5530 objects
Malformed PDF reconstruction succeeded!
```

If cpdf cannot reconstruct a malformed file, it is able to use the gs program to try to reconstruct the PDF file, if you have it installed. For example, if gs is installed and in your path, we might try:

cpdf -gs gs -gs-malformed in.pdf -o out.pdf

To suppress the output of gs use the -gs-quiet option.

If the malformity lies inside an individual page of the PDF, rather than in its gross structure, cpdf may appear to succeed in reconstruction, only to fail when processing a page (e.g when adding text). To force the use of gs to pre-process such files so cpdf cannot fail on them, use -gs-malformed-force:

cpdf in.pdf -gs gs -gs-malformed-force -o out.pdf [-gs-quiet]

The command line for <code>-gs-malformed-force</code> must be of *precisely* this form. Sometimes, on the other hand, we might wish <code>cpdf</code> to fail immediately on any malformed file, rather than try its own reconstruction process. The option <code>-error-on-malformed</code> achieves this.

Sometimes files can be technically well-formed but use inefficient PDF constructs. If you are sure the input files you are using are impeccably formed, the <code>-fast</code> option may be added to the command line (or, if using AND, to each section of the command line). This will use certain shortcuts which speed up processing, but would fail on badly-produced files. The <code>-fast</code> option may be used with:

```
Chapter 3

-rotate-contents -upright -vflip -hflip

-shift -scale-page -scale-to-fit -scale-contents

-show-boxes -hard-box -trim-marks

Chapter 8

-add-text -add-rectangle

-stamp-on -stamp-under -combine-pages

Chapter 9

-impose -impose-xy -twoup -twoup-stack
```

If problems occur, refrain from using -fast.

1.14 Error Handling

When cpdf encounters an error, it exits with code 2. An error message is displayed on stderr (Standard Error). In normal usage, this means it's displayed on the screen. When a bad or inappropriate password is given, the exit code is 1.

1.15 Control Files

```
cpdf -control <filename>
cpdf -args <filename>
```

Some operating systems have a limit on the length of a command line. To circumvent this, or simply for reasons of flexibility, a control file may be specified from which arguments are drawn. This file does not support the full syntax of the command line. Commands are separated by whitespace, quotation marks may be used if an argument contains a space, and the sequence \" may be used to introduce a genuine quotation mark in such an argument.

Several -control arguments may be specified, and may be mixed in with conventional command-line arguments. The commands in each control file are considered in the order in which they are given, after all conventional arguments have been processed. It is recommended to use -args in all new applications. However, -control will be supported for legacy applications.

To avoid interference between <code>-control</code> and <code>AND</code>, a new mechanism has been added. Using <code>-args</code> in place of <code>-control</code> will perform direct textual substitution of the file into the command line, prior to any other processing.

1.16 String Arguments

Command lines are handled differently on each operating system. Some characters are reserved with special meanings, even when they occur inside quoted string arguments. To avoid this

problem, cpdf performs processing on string arguments as they are read.

A backslash is used to indicate that a character which would otherwise be treated specially by the command line interpreter is to be treated literally. For example, Unix-like systems attribute a special meaning to the exclamation mark, so the command line

```
cpdf -add-text "Hello!" in.pdf -o out.pdf
```

would fail. We must escape the exclamation mark with a backslash:

```
cpdf -add-text "Hello\!" in.pdf -o out.pdf
```

It follows that backslashes intended to be taken literally must themselves be escaped (i.e. written $\)$).

1.17 Text Encodings

Some cpdf commands write text to standard output, or read text from the command line or configuration files. These are:

```
-info
-list-bookmarks
-set-author et al.
-list-annotations
-dump-attachments
```

There are three options to control how the text is interpreted:

-utf8 -stripped -raw

Add -utf8 to use Unicode UTF8, -stripped to convert to 7 bit ASCII by dropping any high characters, or -raw to perform no processing. The default unless specified in the documentation for an individual operation is -stripped.

1.18 Font Embedding

Use the <code>-no-embed-font</code> to avoid embedding the Standard 14 Font metrics when adding text with <code>-add-text</code>.

Chapter 2

Merging and Splitting

```
cpdf -merge in1.pdf [<range>] in2.pdf [<range>] [<more names/ranges>]
    [-collate] [-retain-numbering] [-remove-duplicate-fonts]
    [-merge-add-bookmarks [-merge-add-bookmarks-use-titles]]
    -o out.pdf
cpdf -split in.pdf -o <format> [-chunk <chunksize>]
cpdf -split-bookmarks <level> in.pdf -o <format>
```

2.1 Merging

The -merge operation allow the merging of several files into one. Ranges can be used to select only a subset of pages from each input file in the output. The output file consists of the concatenation of all the input pages in the order specified on the command line. Actually, the -merge can be omitted, since this is the default operation of cpdf.

```
cpdf -merge a.pdf 1 b.pdf 2-end -o out.pdf
```

Take page one of a.pdf and all but the first page of b.pdf, merge them and produce out.pdf.

Merge maintains bookmarks, named destinations, and name dictionaries.

PDF features which cannot be merged are retained if they are from the document which first exhibits that feature.

The -collate option collates pages: that is to say, it takes the first page from the first document and its range, then the first page from the second document and its range and so on. When all first pages have been taken, it begins on the second from each range, and so on.

The -retain-numbering option keeps the PDF page numbering labels of each document intact, rather than renumbering the output pages from 1.

The *-remove-duplicate-fonts* option ensures that fonts used in more than one of the inputs only appear once in the output.

The -merge-add-bookmarks option adds a top-level bookmark for each file, using the filename. Any existing bookmarks are retained. The -merge-add-bookmarks-use-titles, when used in conjunction with -merge-add-bookmarks, will use the title from each PDF's metadata instead of the filename.

2.2 Splitting

The *-split* operation splits a PDF file into a number of parts which are written to file, their names being generated from a *format*. The optional *-chunk* option allows the number of pages written to each output file to be set.

```
cpdf -split a.pdf -o out%%%.pdf
```

Split a.pdf to the files out001.pdf, out002.pdf etc.

cpdf a.pdf even AND -split -chunk 10 -o dir/out%%%.pdf

Split the even pages of a.pdf to the files out001.pdf, out002.pdf etc. with at most ten pages in each file. The directory (folder) dir must exist.

If the output format does not provide enough numbers for the files generated, the result is unspecified. The following format operators may be used:

°,	[%] ,	%%% etc.	Sequence number padded to the number of percent signs
		ΘF	Original filename without extension
		QN	Sequence number without padding zeroes
		@ S	Start page of this chunk
		ΘE	End page of this chunk
		ØВ	Bookmark name at this page

Numbers padded to a fixed width field by zeroes may be obtained for @S and @E by following them with more @ signs e.g @E@@@ for a fixed width of three.

2.3 Splitting on Bookmarks

The <code>-split-bookmarks</code> <level> operation splits a PDF file into a number of parts, according to the page ranges implied by the document's bookmarks. These parts are then written to file with names generated from the given format.

Level 0 denotes the top-level bookmarks, level 1 the next level (sub-bookmarks) and so on. So -split-bookmarks 1 creates breaks on level 0 and level 1 boundaries.

```
cpdf -split-bookmarks 0 a.pdf -o out%%%.pdf
Split a.pdf to the files out001.pdf, out002.pdf on bookmark boundaries.
```

Now, there may be many bookmarks on a single page (for instance, if paragraphs are bookmarked or there are two subsections on one page). The splits calculated by <code>-split-bookmarks</code> ensure that each page appears in only one of the output files. It is possible to use the @ operators above, including operator <code>@B</code> which expands to the text of the bookmark:

```
cpdf -split-bookmarks 0 a.pdf -o @B.pdf
```

Split a.pdf on bookmark boundaries, using the bookmark text as the filename.

The bookmark text used for a name is converted from unicode to 7 bit ASCII, and the following characters are removed, in addition to any character with ASCII code less than 32:

/ ? < > \ : * | " ^ + =

2.4 Encrypting with Split and Split Bookmarks

The encryption parameters described in Chapter 4 may be added to the command line to encrypt each split PDF. Similarly, the *-recrypt* switch described in Chapter 1 may by given to re-encrypt each file with the existing encryption of the source PDF.

Chapter 3

Pages

```
cpdf -scale-page "<scale x> <scale y>" [-fast] in.pdf [<range>] -o out.pdf
cpdf -scale-to-fit "<x size> <y size>" [-fast]
     [-scale-to-fit-scale <scale>]
     in.pdf [<range>] -o out.pdf
cpdf -scale-contents [<scale>] [<position>] [-fast]
     in.pdf [<range>] -o out.pdf
cpdf -shift "<shift x> <shift y>" [-fast] in.pdf [<range>] -o out.pdf
cpdf -rotate <angle> in.pdf [<range>] -o out.pdf
cpdf -rotateby <angle> in.pdf [<range>] -o out.pdf
cpdf -rotate-contents <angle> [-fast] in.pdf [<range>] -o out.pdf
cpdf -upright [-fast] in.pdf [<range>] -o out.pdf
cpdf -hflip [-fast] in.pdf [<range>] -o out.pdf
cpdf -vflip [-fast] in.pdf [<range>] -o out.pdf
cpdf -mediabox "<x> <y> <w> <h>" in.pdf [<range>] -o out.pdf
cpdf -cropbox "<x> <y> <w> <h>" in.pdf [<range>] -o out.pdf
cpdf -remove-cropbox in.pdf [<range>] -o out.pdf
   (Also bleed, art, and trim versions of these two commands, for example -artbox,
-remove-trimbox)
cpdf -frombox <boxname> -tobox <boxname> [-mediabox-if-missing]
     in.pdf [<range>] -o out.pdf
cpdf -hard-box <boxname> [-fast] in.pdf [<range>]
     [-mediabox-if-missing] -o out.pdf
cpdf -show-boxes [-fast] in.pdf [<range>] -o out.pdf
cpdf -trim-marks [-fast] in.pdf [<range>] -o out.pdf
```

3.1 Page Sizes

Any time when a page size is required, instead of writing, for instance "210mm 197mm" one can instead write a4portrait. Here is a list of supported page sizes:

a0portrait a3portrait a6portrait a9portrait	alportrait a4portrait a7portrait a10portrait	a2portrait a5portrait a8portrait
asportrait	aiopoiciaic	
a0landscape a3landscape a6landscape a9landscape	allandscape a4landscape a7landscape a10landscape	a2landscape a5landscape a8landscape
usletterportrait uslegalportrait	usletterlandscape uslegallandscape	

3.2 Scale Pages

The *-scale-page* operation scales each page in the range by the X and Y factors given. This scales both the page contents, and the page size itself. It also scales any Crop Box and other boxes (Art Box, Trim Box etc). As with several of these commands, remember to take into account any page rotation when considering what the X and Y axes relate to.

cpdf -scale-page "2 2" in.pdf -o out.pdf

Convert an A4 page to A3, for instance.

The <code>-scale-to-fit</code> operation scales each page in the range to fit a given page size, preserving aspect ratio and centering the result.

cpdf -scale-to-fit "297mm 210mm" in.pdf -o out.pdf cpdf -scale-to-fit a4portrait in.pdf -o out.pdf

Scale a file's pages to fit A4 portrait.

The scale can optionally be set to a percentage of the available area, instead of filling it.

```
cpdf -scale-to-fit a4portrait -scale-to-fit-scale 0.9 in.pdf -o out.pdf
Scale a file's pages to fit A4 portrait, scaling the page 90% of its possible size.
```

NB: -scale-to-fit operates with respect to the media box not the crop box. If necessary, set the media box to be equal to the crop box first. In addition, -scale-to-fit presently requires that the origin of the media box be (0, 0). This can be assured by preprocessing with -upright.

The -scale-contents operation scales the contents about the center of the crop box (or, if absent, the media box), leaving the page dimensions (boxes) unchanged.

```
cpdf -scale-contents 0.5 in.pdf -o out.pdf
```

Scale a file's contents on all pages to 50% of its original dimensions.

To scale about a point other than the center, one can use the positioning commands described in Section 8.2.4. For example:

```
cpdf -scale-contents 0.5 -topright 20 in.pdf -o out.pdf
```

Scale a file's contents on all pages to 50% of its original dimensions about a point 20pts from its top right corner.

3.3 Shift Page Contents

The *-shift* operation shifts the contents of each page in the range by X points horizontally and Y points vertically.

cpdf -shift "50 0" in.pdf even -o out.pdf

Shift pages to the right by 50 points (for instance, to increase the binding margin).

3.4 Rotating Pages

There are two ways of rotating pages: (1) setting a value in the PDF file which asks the viewer (e.g. Acrobat) to rotate the page on-the-fly when viewing it (use -rotate or -rotateby) and (2) actually rotating the page contents and/or the page dimensions (use -upright afterwards or -rotate-contents to just rotate the page contents).

The possible values for -rotate and -rotate-by are 0, 90, 180 and 270, all interpreted as being clockwise. Any value may be used for -rotate-contents.

The -rotate operation sets the viewing rotation of the selected pages to the absolute value given.

```
cpdf -rotate 90 in.pdf -o out.pdf
```

Set the rotation of all the pages in the input file to ninety degrees clockwise.

The -rotateby operation changes the viewing rotation of all the given pages by the relative value given.

cpdf -rotateby 90 in.pdf -o out.pdf

Rotate all the pages in the input file by ninety degrees clockwise.

The -rotate-contents operation rotates the contents and dimensions of the page by the given relative value.

cpdf -rotate-contents 90 in.pdf -o out.pdf

Rotate all the page contents in the input file by ninety degrees clockwise. Does not change the page dimensions.

The -upright operation does whatever combination of -rotate and -rotate-contents is required to change the rotation of the document to zero without altering its appearance. In addition, it makes sure the media box has its origin at (0,0), changing other boxes to compensate. This is important because some operations in CPDF (such as scale-to-fit), and in other PDF-processing programs, work properly only when the origin is (0, 0).

3.5 Flipping Pages

The -hflip and -vflip operations flip the contents of the chosen pages horizontally or vertically. No account is taken of the current page rotation when considering what "horizontally" and "vertically" mean, so you may like to use -upright first.

```
cpdf -hflip in.pdf even -o out.pdf
Flip the even pages in in.pdf horizontally.
    cpdf -vflip in.pdf -o out.pdf
Flip all the pages in in.pdf vertically.
```

3.6 Boxes and Cropping

All PDF files contain a *media box* for each page, giving the dimensions of the paper. To change these dimensions (without altering the page contents in any way), use the <code>-mediabox</code> operation.

```
cpdf -mediabox "Opt Opt 500pt 500pt" in.pdf -o out.pdf
```

Set the media box to 500 points square.

The four numbers are minimum x, minimum y, width, height. x coordinates increase to the right, y coordinates increase upwards. PDF file can also optionally contain a *crop box* for each

page, defining to what extent the page is cropped before being displayed or printed. A crop box can be set, changed and removed, without affecting the underlying media box. To set or change the crop box use -cropbox. To remove any existing crop box, use -remove-cropbox.

```
cpdf -cropbox "Opt Opt 200mm 200mm" in.pdf -o out.pdf
Crop pages to the bottom left 200-millimeter square of the page.
```

```
cpdf -remove-cropbox in.pdf -o out.pdf
```

Remove cropping.

Note that the crop box is only obeyed in some viewers. Similar operations are available for the bleed, art, and trim boxes (-art, -remove-bleed etc.)

Copy the contents of one box to another.

This operation copies the contents of one box (Media box, Crop box, Trim box etc.) to another. If -mediabox-if-missing is added, the media box will be substituted when the 'from' box is not set for a given page. For example

cpdf -frombox /TrimBox -tobox /CropBox in.pdf -o out.pdf

copies the Trim Box of each page to the Crop Box of each page. The possible boxes are /MediaBox, /CropBox, /BleedBox, /TrimBox, /ArtBox.

A hard box (one which clips its contents by inserting a clipping rectangle) may be created with the -hard-box operation:

cpdf -hard-box /TrimBox in.pdf -o out.pdf

This means the resultant file may be used as a stamp without contents outside the given box reappearing. The <code>-mediabox-if-missing</code> option may also be used here.

3.7 Showing Boxes and Printer's Marks

The -show-boxes operation displays the boxes present on each page as method of debugging. Since boxes may be coincident, they are shown in differing colours and dash patterns so they may be identified even where they overlap. The colours are:

Media box	Red
Crop box	Green
Art box	Blue
Trim box	Orange
Bleed box	Pink

The -trim-marks operation adds trim marks to a PDF file. The trim box must be present.

Encryption and Decryption

```
cpdf -encrypt <method> [-pw=]<owner> [-pw=]<user>
    [-no-encrypt-metadata] <permissions> in.pdf -o out.pdf
cpdf -decrypt [-decrypt-force] in.pdf owner=<owner password> -o out.pdf
```

4.1 Introduction

PDF files can be encrypted using various types of encryption and attaching various permissions describing what someone can do with a particular document (for instance, printing it or extracting content). There are two types of person:

The User can do to the document what is allowed in the permissions.

The **Owner** can do anything, including altering the permissions or removing encryption entirely.

There are five kinds of encryption:

- 40-bit encryption (method 40bit) in Acrobat 3 (PDF 1.1) and above
- 128-bit encryption (method 128bit) in Acrobat 5 (PDF 1.4) and above
- 128-bit AES encryption (method AES) in Acrobat 7 (PDF 1.6) and above
- 256-bit AES encryption (method AES256) in Acrobat 9 (PDF 1.7) *this is deprecated do not use for new documents*
- 256-bit AES encryption (method AES256ISO) in PDF 2.0

All encryption supports these kinds of permissions:

-no-edit	Cannot change the document
-no-print	Cannot print the document
-no-copy	Cannot select or copy text or graphics
-no-annot	Cannot add or change form fields or annotations

In addition, 128-bit encryption (Acrobat 5 and above) and AES encryption supports these:

-no-forms	Cannot edit form fields
-no-extract	Cannot extract text or graphics
-no-assemble	Cannot merge files etc.
-no-hq-print	Cannot print high-quality

Add these options to the command line to prevent each operation.

4.2 Encrypting a Document

To encrypt a document, the owner and user passwords must be given (here, fred and charles respectively):

```
cpdf -encrypt 40bit fred charles -no-print in.pdf -o out.pdf
cpdf -encrypt 128bit fred charles -no-extract in.pdf -o out.pdf
cpdf -encrypt AES fred "" -no-edit -no-copy in.pdf -o out.pdf
```

A blank user password is common. In this event, PDF viewers will typically not prompt for a password for when opening the file or for operations allowable with the user password.

cpdf -encrypt AES256 fred "" -no-forms in.pdf -o out.pdf

In addition, the usual method can be used to give the existing owner password, if the document is already encrypted.

The optional -pw= preface may be given where a password might begin with a – and thus be confused with a command line option.

When using AES encryption, the option is available to refrain from encrypting the metadata. Add -no-encrypt-metadata to the command line.

4.3 Decrypting a Document

To decrypt a document, the owner password is provided.

```
cpdf -decrypt in.pdf owner=fred -o out.pdf
```

The user password cannot decrypt a file.

When appropriate passwords are not available, the option <code>-decrypt-force</code> may be added to the command line to process the file regardless.

Compression

```
cpdf -decompress in.pdf -o out.pdf
cpdf -compress in.pdf -o out.pdf
cpdf -squeeze in.pdf [-squeeze-log-to <filename>]
    [-squeeze-no-recompress] [-squeeze-no-page-data] -o out.pdf
```

cpdf provides basic facilities for decompressing and compressing PDF streams, and for reprocessing the whole file to 'squeeze' it.

5.1 Decompressing a Document

To decompress the streams in a PDF file, for instance to manually inspect the PDF, use:

cpdf -decompress in.pdf -o out.pdf

If cpdf finds a compression type it can't cope with, the stream is left compressed. When using -decompress, object streams are not compressed. It may be easier for manual inspection to also remove object streams, by adding the -no-preserve-objstm option to the command.

5.2 Compressing a Document

To compress the streams in a PDF file, use:

```
cpdf -compress in.pdf -o out.pdf
```

cpdf compresses any streams which have no compression using the **FlateDecode** method, with the exception of Metadata streams, which are left uncompressed.

5.3 Squeezing a Document

To *squeeze* a PDF file, reducing its size by an average of about twenty percent (though sometimes not at all), use:

```
cpdf -squeeze in.pdf -o out.pdf
```

Adding -squeeze to the command line when using another operation will *squeeze* the file or files upon output.

The -squeeze operation writes some information about the squeezing process to standard output. The squeezing process involves several processes which losslessly attempt to reduce the file size. It is slow, so should not be used without thought.

```
$ ./cpdf -squeeze in.pdf -o out.pdf
Initial file size is 238169 bytes
Beginning squeeze: 123847 objects
Squeezing... Down to 114860 objects
Squeezing ... Down to 114842 objects
Squeezing page data
Recompressing document
Final file size is 187200 bytes, 78.60% of original.
```

The -squeeze-log-to <filename> option writes the log to the given file instead of to standard output. Log contents is appended to the end of the log file, preserving existing contents.

There are two options which turn off parts of the squeezer. They are -squeeze-no-recompress for avoiding the reprocessing of malformed compressed sections, and -squeeze-no-page-data for avoiding the reprocessing of malformed page data.

Bookmarks

```
cpdf -list-bookmarks [-utf8 | -raw] in.pdf
cpdf -list-bookmarks-json in.pdf
cpdf -remove-bookmarks in.pdf -o out.pdf
cpdf -add-bookmarks <bookmark file> in.pdf -o out.pdf
cpdf -add-bookmarks-json <bookmark file> in.pdf -o out.pdf
cpdf -bookmarks-open-to-level <n> in.pdf -o out.pdf
cpdf -table-of-contents [-toc-title] [-toc-no-bookmark]
[-font <font>] [-font-size <size>] in.pdf -o out.pdf
```

PDF bookmarks (properly called the *document outline*) represent a tree of references to parts of the file, typically displayed at the side of the screen. The user can click on one to move to the specified place. cpdf provides facilities to list, add, and remove bookmarks. The format used by the list and add operations is the same, so you can feed the output of one into the other, for instance to copy bookmarks.

6.1 List Bookmarks

The -list-bookmarks operation prints (to standard output) the bookmarks in a file. The first column gives the level of the tree at which a particular bookmark is. Then the text of the bookmark in quotes. Then the page number which the bookmark points to. Then (optionally) the word "open" if the bookmark should have its children (at the level immediately below) visible when the file is loaded. Then the destination (see below). For example, upon executing

```
cpdf -list-bookmarks doc.pdf
```

the result might be:

```
0 "Part 1" 1 open
1 "Part 1A" 2 "[2 /XYZ 200 400 null]"
1 "Part 1B" 3
0 "Part 2" 4
1 "Part 2a" 5
```

If the page number is 0, it indicates that clicking on that entry doesn't move to a page.

By default, cpdf converts unicode to ASCII text, dropping characters outside the ASCII range. To prevent this, and return unicode UTF8 output, add the -utf8 option to the command. To prevent any processing, use the -raw option. See Section 1.17 for more information. A newline in a bookmark is represented as "\n".

By using <code>-list-bookmarks-json</code> instead, the bookmarks are formatted as a JSON array, in order, of dictionaries formatted thus:

```
{ "level": 0,
  "text": "1 Basic Usage",
  "page": 17,
  "open": false,
  "target":
    [ { "I": 17 },
        { "N": "/XYZ" },
        { "F": 85.039 },
        { "F": 609.307 },
        null ]
}
```

See chapter 15 for more details of cpdf's JSON formatting. Bookmark text in JSON bookmarks, however, is in UTF8 for ease of use.

6.1.1 Destinations

The destination is an extended description of where the bookmark should point to (i.e it can be more detailed than just giving the page). For example, it may point to a section heading halfway down a page. Here are the possibilities:

Format	Description
[p /XYZ left top zoom]	Display page number <i>p</i> with (<i>left, top</i>) positioned at upper-left of window and magnification of <i>zoom</i> . Writing "null" for any of <i>left, top</i> or <i>zoom</i> specifies no
[<i>p</i> /Fit]	change. A <i>zoom</i> of 0 is the same as "null". Display page number <i>p</i> so as to fit fully within the window.
[p /FitH top]	Display page number <i>p</i> with vertical coordinate <i>top</i> at the top of the window and the page magnified so its width fits the window. A null value for <i>top</i> implies no change.
[p / FitV left]	Display page number p with horizontal coordinate <i>left</i> at the left of the window, and the page magnified so its height fits the window. A null value for <i>left</i> implies no change.
[p /FitR left bottom right top]	Display page number p magnified so as to fit entirely within the rectangle specified by the other parameters.
[<i>p</i> /FitB]	As for /Fit but with the page's bounding box (see below).
[p /FitBH top]	As for /FitH but with the page's bounding box (see below).
[p /FitBV left]	As for /FitV but with the page's bounding box (see below).

The *bounding box* is the intersection of the page's crop box and the bounding box of the page contents. Some other kinds of destination may be produced by <code>-list-bookmarks</code>. They will be preserved by <code>-add-bookmarks</code> and may be edited as your risk.

6.2 Remove Bookmarks

The -remove-bookmarks operations removes all bookmarks from the file.

cpdf -remove-bookmarks in.pdf -o out.pdf

6.3 Add Bookmarks

The -add-bookmarks file adds bookmarks as specified by a *bookmarks file*, a text file in ASCII or UTF8 encoding and in the same format as that produced by the -list-bookmarks operation. If there are any bookmarks in the input PDF already, they are discarded. For example, if the file bookmarks.txt contains the output from -list-bookmarks above, then the command

cpdf -add-bookmarks bookmarks.txt in.pdf -o out.pdf

adds the bookmarks to the input file, writing to out.pdf. An error will be given if the bookmarks file is not in the correct form (in particular, the numbers in the first column which specify the level must form a proper tree with no entry being more than one greater than the last).

Bookmarks in JSON format (see above) may be added with -add-bookmarks-json:

```
cpdf -add-bookmarks-json bookmarks.json in.pdf -o out.pdf
```

Remember that strings in JSON bookmark files are in UTF8, rather than as native PDF strings.

6.4 Opening bookmarks

As an alternative to extracting a bookmark file and manipulating the open-status of bookmarks, mass manipulation may be achieved by the following operation:

cpdf -bookmarks-open-to-level <level> in.pdf -o out.pdf

A level of 0 will close all bookmarks, level 1 will open just the top level, closing all others etc. To open all of them, pick a sufficiently large level.

6.5 Making a Table of Contents

Cpdf can automatically generate a table of contents from existing bookmarks, adding it to the beginning of the document.

cpdf -table-of-contents in.pdf -o out.pdf

The page(s) added will have the same dimensions, media and crop boxes as the first page of the original file. The default title is "Table of Contents", though this may be changed:

cpdf -table-of-contents -toc-title "Contents" in.pdf -o out.pdf

An empty title removes the title. The sequence \n may be used to split the title into lines. The default font is 12pt Times Roman (and 24pt for the title). The base font and size may be changed with -font and -font-size (see chapter 8 for full details):

cpdf -table-of-contents -font "Courier-Bold" -font-size 8
 in.pdf -o out.pdf

By default, an entry for the new table of contents will be added to the document's bookmarks. To suppress this behaviour, add -toc-no-bookmark:

cpdf -table-of-contents -toc-no-bookmark in.pdf -o out.pdf

Presentations

```
cpdf -presentation in.pdf [<range>] -o out.pdf
    [-trans <transition-name>] [-duration <float>]
    [-vertical] [-outward] [-direction <int>]
    [-effect-duration <float>]
```

The PDF file format, starting at Version 1.1, provides for simple slide-show presentations in the manner of Microsoft Powerpoint. These can be played in Acrobat and possibly other PDF viewers, typically started by entering full-screen mode. The -presentation operation allows such a presentation to be built from any PDF file.

The -trans option chooses the transition style. When a page range is used, it is the transition *from* each page named which is altered. The following transition styles are available:

- **Split** Two lines sweep across the screen, revealing the new page. By default the lines are horizontal. Vertical lines are selected by using the -vertical option.
- **Blinds** Multiple lines sweep across the screen, revealing the new page. By default the lines are horizontal. Vertical lines are selected by using the -vertical option.
- **Box** A rectangular box sweeps inward from the edges of the page. Use -outward to make it sweep from the center to the edges.
- Wipe A single line sweeps across the screen from one edge to the other in a direction specified by the -direction option.
- **Dissolve** The old page dissolves gradually to reveal the new one.
- Glitter The same as Dissolve but the effect sweeps across the page in the direction specified by the -direction option.

To remove a transition style currently applied to the selected pages, omit the -trans option.

The *-effect-duration* option specifies the length of time in seconds for the transition itself. The default value is one second.

The -duration option specifies the maximum time in seconds that the page is displayed before the presentation automatically advances. The default, in the absence of the -duration option, is for no automatic advancement.

The -direction option (for **Wipe** and **Glitter** styles only) specifies the direction of the effect. The following values are valid:

0 Left to right

90 Bottom to top (Wipe only)

180 Right to left (Wipe only)

270 Top to bottom

315 Top-left to bottom-right (Glitter only)

For example:

cpdf -presentation in.pdf 2-end -trans Split -duration 10 -o out.pdf

The **Split** style, with vertical lines, and each slide staying ten seconds unless manually advanced. The first page (being a title) does not move on automatically, and has no transition effect.

To use different options on different page ranges, run cpdf multiple times on the file using a different page range each time.

Watermarks and Stamps

```
cpdf -stamp-on source.pdf
     [-scale-stamp-to-fit] [<positioning command>] [-relative-to-cropbox]
     in.pdf [<range>] [-fast] -o out.pdf
cpdf -stamp-under source.pdf
     [-scale-stamp-to-fit] [<positioning command>] [-relative-to-cropbox]
     in.pdf [<range>] [-fast] -o out.pdf
cpdf -combine-pages over.pdf under.pdf [-fast] -o out.pdf
cpdf ([-add-text <text-format> | -add-rectangle <size>])
                                   [-font-size <size-in-points>]
[-line-spacing <number>]
              [-font <fontname>]
              [-color <color>]
                                         [-linewidth <number>]
              [-outline]
              [-underneath]
                                         [-relative-to-cropbox]
                                         [-bates <number>]
              [-prerotate]
              [-bates-at-range <number>] [-bates-pad-to <number>]
              [-opacity <number>] [-midline]
              [-topline]
                                           [-fast]
              in.pdf [<range>] -o out.pdf
See also positioning commands below.
cpdf -remove-text in.pdf [<range>] -o out.pdf
cpdf -prepend-content <content> in.pdf [<range>] -o out.pdf
cpdf -postpend-content <content> in.pdf [<range>] -o out.pdf
cpdf -stamp-as-xobject stamp.pdf in.pdf [<range>] -o out.pdf
NB: See discussion of -fast in Section 1.13.
```

8.1 Add a Watermark or Logo

The <code>-stamp-on</code> and <code>-stamp-under</code> operations stamp the first page of a source PDF onto or under each page in the given range of the input file. For example,

cpdf -stamp-on logo.pdf in.pdf odd -o out.pdf

stamps the file logo.pdf onto the odd pages of in.pdf, writing to out.pdf. A watermark should go underneath each page:

cpdf -stamp-under topsecret.pdf in.pdf -o out.pdf

The position commands in Section 8.2.4 can be used to locate the stamp more precisely (they are calculated relative to the crop box of the stamp). Or, preprocess the stamp with -shift first.

The <code>-scale-stamp-to-fit</code> option can be added to scale the stamp to fit the page before applying it. The use of positioning commands together with <code>-scale-stamp-to-fit</code> is not recommended.

The -combine-pages operation takes two PDF files and stamps each page of one over each page of the other. The length of the output is the same as the length of the "under" file. For instance:

cpdf -combine-pages over.pdf under.pdf -o out.pdf

Page attributes (such as the display rotation) are taken from the "under" file. For best results, remove any rotation differences in the two files using -upright first.

The -relative-to-cropbox option takes the positioning command to be relative to the crop box of each page rather than the media box.

8.2 Stamp Text, Dates and Times.

The -add-text operation allows text, dates and times to be stamped over one or more pages of the input at a given position and using a given font, font size and color.

cpdf -add-text "Copyright 2014 ACME Corp." in.pdf -o out.pdf

The default is black 12pt Times New Roman text in the top left of each page. The text can be placed underneath rather than over the page by adding the <code>-underneath</code> option.

Text previously added by cpdf may be removed by the -remove-text operation.

cpdf -remove-text in.pdf -o out.pdf

8.2.1 Page Numbers

There are various special codes to include the page number in the text:

%Page	Page number in arabic notation $(1, 2, 3)$
%PageDiv2	Page number in arabic notation divided by two
%roman	Page number in lower-case roman notation (i, ii, iii)
%Roman	Page number in upper-case roman notation (I, II, III)
%EndPage	Last page of document in arabic notation
%Label	The page label of the page
%EndLabel	The page label of the last page
%filename	The full file name of the input document

For example, the format "Page %Page of %EndPage" might become "Page 5 of 17".

NB: In some circumstances (e.g in batch files) on Microsoft Windows, % is a special character, and must be escaped (written as %%). Consult your local documentation for details.

8.2.2 Date and Time Formats

- %a Abbreviated weekday name (Sun, Mon etc.)
- %A Full weekday name (Sunday, Monday etc.)
- %b Abbreviated month name (Jan, Feb etc.)
- **%B** Full month name (January, February etc.)
- %d Day of the month (01–31)
- Se Day of the month (1-31)
- H Hour in 24-hour clock (00–23)
- I Hour in 12-hour clock (01–12)
- %j Day of the year (001–366)
- %m Month of the year (01–12)
- M Minute of the hour (00–59)
- %p "a.m" or "p.m"
- Second of the minute (00–61)
- %T Same as %H:%M:%S
- %u Weekday (1–7, 1 = Sunday)
- %w Weekday (0−6, 0 = Sunday)
- %Y Year (0000–9999)
- %% The % character.

8.2.3 Bates Numbers

Unique page identifiers can be specified by putting %Bates in the format. The starting point can be set with the -bates option. For example:

cpdf -add-text "Page ID: %Bates" -bates 23745 in.pdf -o out.pdf

To specify that bates numbering begins at the first page of the range, use <code>-bates-at-range</code> instead. This option must be specified after the range is specified. To pad the bates number up to a given number of leading zeros, use <code>-bates-pad-to</code> in addition to either <code>-bates</code> or <code>-bates-at-range</code>.

8.2.4 Position

The position of the text may be specified either in absolute terms:

-pos-center "200 200"

Position the center of the baseline text at (200pt, 200pt)

-pos-left "200 200"

Position the left of the baseline of the text at (200pt, 200pt)

-pos-right "200 200"

Position the right of the baseline of the text at (200pt, 200pt)

Positions relative to certain common points can be set:

-top 10	Center of baseline 10 pts down from the top center
-topleft 10	Left of baseline 10 pts down and in from top left
-topright 10	Right of baseline 10 pts down and left from top right
-left 10	Left of baseline 10 pts in from center left
-bottomleft 10	Left of baseline 10 pts in and up from bottom left
-bottom 10	Center of baseline 10 pts up from bottom center
-bottomright 10	Right of baseline 10 pts up and in from bottom right
-right 10	Right of baseline 10 pts in from the center right
-diagonal	Diagonal, bottom left to top right, centered on page
-reverse-diagonal	Diagonal, top left to bottom right, centered on page
-center	Centered on page

No attempt is made to take account of the page rotation when interpreting the position, so -prerotate must be added to the command line if the file contains pages with a non-zero viewing rotation. This is equivalent to pre-processing the document with -upright.

The <code>-relative-to-cropbox</code> modifier can be added to the command line to make these measurements relative to the crop box instead of the media box.

The default position is equivalent to -topleft 100.

The -midline option may be added to specify that the positioning commands above are to be considered relative to the midline of the text, rather than its baseline. Similarly, the -topline option may be used to specify that the position is taken relative to the top of the text.

8.2.5 Font and Size

The font may be set with the -font option. The 14 Standard PDF fonts are available:

Times-Roman Times-Bold Times-Italic Times-BoldItalic Helvetica Helvetica-Bold Helvetica-Oblique Helvetica-BoldOblique Courier Courier-Bold Courier-Oblique Courier-BoldOblique Symbol ZapfDingbats

For example, page numbers in Times Italic can be achieved by:

cpdf -add-text "-%Page-" -font "Times-Italic" in.pdf -o out.pdf

See Section 14.3 for how to use other fonts. The font size can be altered with the -font-size option, which specifies the size in points:

cpdf -add-text "-%Page-" -font-size 36 in.pdf -o out.pdf

8.2.6 Colors

The *-color* option takes an RGB (3 values), CYMK (4 values), or Grey (1 value) color. Components range between 0 and 1. The following RGB colors are predefined:

Color	R, G, B
white	1, 1, 1
black	0,0,0
red	1, 0, 0
green	0, 1, 0
blue	0, 0, 1

```
cpdf -add-text "Hullo" -color "red" in.pdf -o out.pdf
cpdf -add-text "Hullo" -color "0.5 0.5 0.5" in.pdf -o out.pdf
cpdf -add-text "Hullo" -color "0.75" in.pdf -o out.pdf
cpdf -add-text "Hullo" -color "0.5 0.5 0.4 0.9" in.pdf -o out.pdf
```

Partly-transparent text may be specified using the -opacity option. Wholly opaque is 1 and wholly transparent is 0. For example:

cpdf -add-text "DRAFT" -color "red" -opacity 0.3 -o out.pdf

8.2.7 Outline Text

The -outline option sets outline text. The line width (default 1pt) may be set with the -linewidth option. For example, to stamp documents as drafts:

cpdf -add-text "DRAFT" -diagonal -outline in.pdf -o out.pdf

8.2.8 Multi-line Text

The code \n can be included in the text string to move to the next line. In this case, the vertical position refers to the baseline of the first line of text (if the position is at the top, top left or top right of the page) or the baseline of the last line of text (if the position is at the bottom, bottom left or bottom right).

The -midline option may be used to make these vertical positions relative to the midline of a line of text rather than the baseline, as usual.

The -line-spacing option can be used to increase or decrease the line spacing, where a spacing of 1 is the standard.

Justification of multiple lines is handled by the <code>-justify-left,-justify-right</code> and <code>-justify-center</code> options. The defaults are left justification for positions relative to the left hand side of the page, right justification for those relative to the right, and center justification for positions relative to the center of the page. For example:

8.2.9 Special Characters

If your command line allows for the inclusion of unicode characters, the input text will be considered as UTF8 by cpdf. Special characters which exist in the PDF WinAnsiEncoding Latin 1 code (such as many accented characters) will be reproduced in the PDF. This does not mean, however, that every special character can be reproduced – it must exist in the font. When using a custom font, cpdf will attempt to convert from UTF8 to the encoding of that font automatically.

(For compatibility with previous versions of cpdf, special characters may be introduced manually with a backslash followed by the three-digit octal code of the character in the PDF WinAnsiEncoding Latin 1 Code. The full table is included in Appendix D of the Adobe PDF Reference Manual, which is available at https://wwwimages2.adobe.com/content/dam/acom/en/devnet/pdf/pdfs/PDF32000_2008.pdf. For example, a German sharp s (ß) may be introduced by \337.)

8.3 Stamping Graphics

A rectangle may be placed on one or more pages by using the <code>-add-rectangle <size></code> command. Most of the options discussed above for text placement apply in the same way. For example:

This can be used to blank out or highlight part of the document. The following positioning options work as you would expect: -topleft, -top, -topright, -right, -bottomright, -bottom, -bottomleft, -left, -center. When using the option -pos-left "x y", the point (x, y) refers to the bottom-left of the rectangle. When using the option -pos-right "x y", the point (x, y) refers to the bottom-right of the rectangle. When using the option -pos-right -pos-center "x y", the point (x, y) refers to the bottom-right of the rectangle. When using the option -pos-center "x y", the point (x, y) refers to the center of the rectangle. The options -diagonal and -reverse-diagonal have no meaning.

8.4 Low-level facilities

These two operations add content directly to the beginning or end of the page data for a page. You must understand the PDF page description language to use these.

```
cpdf -prepend-content <content> in.pdf [<range>] -o out.pdf
cpdf -postpend-content <content> in.pdf [<range>] -o out.pdf
```

The -fast option may be added (see Chapter 1). The -stamp-as-xobject operation puts a file in another as a Form XObject on the given pages. You can then use -prepend-content or -postpend-content to use it.

cpdf -stamp-as-xobject stamp.pdf in.pdf [<range>] -o out.pdf

Multipage Facilities

```
cpdf -pad-before in.pdf [<range>] [-pad-with pad.pdf] -o out.pdf
cpdf -pad-after in.pdf [<range>] [-pad-with pad.pdf] -o out.pdf
cpdf -pad-every [<integer>] in.pdf [-pad-with pad.pdf] -o out.pdf
cpdf -pad-multiple [<integer>] in.pdf -o out.pdf
cpdf -pad-multiple-before [<integer>] in.pdf -o out.pdf
cpdf [-impose <pagesize> | impose-xy <x y>]
[-impose-columns] [-impose-rtl] [-impose-btt]
[-impose-margin <margin>] [-impose-spacing <spacing>]
[-impose-linewidth <width>] [-fast]
in.pdf -o out.pdf
cpdf -twoup-stack [-fast] in.pdf -o out.pdf
```

9.1 Inserting Blank Pages

Sometimes, for instance to get a printing arrangement right, it's useful to be able to insert blank pages into a PDF file. cpdf can add blank pages before a given page or pages, or after. The pages in question are specified by a range in the usual way:

cpdf -pad-before in.pdf 1 -o out.pdf

Add a blank page before page 1 (i.e. at the beginning of the document.)

cpdf -pad-after in.pdf 2,16,38,84,121,147 -o out.pdf

Add a blank page after pages 2, 16, 38, 84, 121 and 147 (for instance, to add a clean page between chapters of a document.)

The dimensions of the padded page are derived from the boxes (media box, crop box etc.) of the page after or before which the padding is to be applied.

The -pad-every n operation places a blank page after every n pages, excluding any last one. For example...

```
cpdf -pad-every 3 in.pdf -o out.pdf
```

Add a blank page after every three pages

... on a 9 page document adds a blank page after pages 3 and 6.

In all three of these operations, one may specify <code>-pad-with</code> providing a (usually onepage) PDF file to be used instead of a blank page. For example, a page saying "This page left intentionally blank".

The -pad-multiple n operation adds blank pages so the document has a multiple of n pages. For example:

cpdf -pad-multiple 8 in.pdf -o out.pdf

Add blank pages to in.pdf so it has a multiple of 8 pages.

The -pad-multiple-before n operation adds the padding pages at the beginning of the file instead.

9.2 Imposition

Imposition is the act of putting two or more pages of an input document onto each page of the output document. There are two operations provided by cpdf:

- the -impose operation which, given a page size fits multiple pages into it; and
- the -impose-xy operation which, given an *x* and *y* value, builds an output page which fits *x* input pages horizontally and *y* input pages vertically.

cpdf -impose a0landscape in.pdf -o out.pdf

Impose as many pages as will fit on to new A0 landscape pages.

cpdf -impose-xy "3 4" in.pdf -o out.pdf

Impose 3 across and 4 down on to new pages of 3 times the width and 4 times the height of the input ones.

The *x* value for -impose-xy may be set to zero to indicate an infinitely-wide page; the *y* value to indicate an infinitely-long one.

In both cases, the pages in the input file are assumed to be of the same dimensions. The following options may be used to modify the output:

- -impose-columns Lay the pages out in columns rather than rows.
- -impose-rtl Lay the pages out right-to-left.
- -impose-btt Lay the pages out bottom-to-top.
- -impose-margin <margin> Add a margin around the edge of the page of the given width. When using -impose-xy the page size increases; with -impose the pages are scaled.
- -impose-spacing <spacing> Add spacing between each row and column. When using -impose-xy the page size increases; with -impose the pages are scaled.
- -impose-linewidth <width> Add a border around each input page. With -impose the pages are scaled after the border is added, so you must account for this yourself.

To impose with rotated pages, for example to put two A4 portrait pages two-up on an A3 landscape page, rotate them prior to imposition.

Two other ways of putting multiple pages on a single page remain from earlier versions of cpdf which lacked a general imposition operation. The -twoup-stack operation puts two logical pages on each physical page, rotating them 90 degrees to do so. The new mediabox is thus larger. The -twoup operation does the same, but scales the new sides down so that the media box is unchanged.

```
cpdf -two-up in.pdf -o out.pdf
```

Impose a document two-up, keeping the existing page size.
 cpdf -two-up-stack in.pdf -o out.pdf

Impose a document two-up on a larger page by rotation.

NB: For all imposition options, see also discussion of -fast in Section 1.13.

Annotations

```
cpdf -list-annotations in.pdf [<range>]
cpdf -copy-annotations from.pdf to.pdf [<range>] -o out.pdf
cpdf -remove-annotations in.pdf [<range>] -o out.pdf
```

10.1 List Annotations

The *-list-annotations* operation prints the textual content of any annotations on the selected pages to standard output. Each annotation is preceded by the page number and followed by a newline. See Section 1.17 for more information on text encodings in the output of this operation.

cpdf -list-annotations in.pdf > annots.txt

Print annotations from in.pdf, redirecting output to annots.txt.

10.2 Copy Annotations

The *-copy-annotations* operation copies the annotations in the given page range from one file (the file specified immediately after the option) to another pre-existing PDF. The range is specified after this pre-existing PDF. The result is then written an output file, specified in the usual way.

cpdf -copy-annotations from.pdf to.pdf 1-10 -o result.pdf

Copy annotations from the first ten pages of from.pdf onto the PDF file to.pdf, writing the result to results.pdf.

10.3 Remove Annotations

The *-remove-annotations* operation removes all annotations from the given page range.

cpdf -remove-annotations in.pdf 1 -o out.pdf

Remove annotations from the first page of a file only.

Document Information and Metadata

```
cpdf -info [-raw | -utf8] in.pdf
cpdf -page-info in.pdf
cpdf -pages in.pdf
cpdf -set-title <title of document>
     [-also-set-xmp] [-just-set-xmp] [-raw] in.pdf -o out.pdf
(Also -set-author etc. See Section 11.2.)
cpdf -set-page-layout <layout> in.pdf -o out.pdf
cpdf -set-page-mode <mode> in.pdf -o out.pdf
cpdf -hide-toolbar <true | false> in.pdf -o out.pdf
     -hide-menubar
     -hide-window-ui
     -fit-window
     -center-window
     -display-doc-title
cpdf -open-at-page <page number> in.pdf -o out.pdf
cpdf -open-at-page-fit <page number> in.pdf -o out.pdf
cpdf -set-metadata <metadata-file> in.pdf -o out.pdf
cpdf -remove-metadata in.pdf -o out.pdf
cpdf -print-metadata in.pdf
cpdf -create-metadata in.pdf -o out.pdf
cpdf -set-metadata-date <date> in.pdf -o out.pdf
cpdf -add-page-labels in.pdf -o out.pdf
     [-label-style <style>] [-label-prefix <string>]
     [-label-startval <integer>] [-labels-progress]
```

```
cpdf -remove-page-labels in.pdf -o out.pdf
cpdf -print-page-labels in.pdf
```

11.1 Reading Document Information

The -info operation prints entries from the document information dictionary, and from any XMP metadata to standard output.

```
$cpdf -info pdf_reference.pdf
Encryption: 40bit
Linearized: true
Permissions: No edit
Version: 1.6
Pages: 1310
Title: PDF Reference, version 1.7
Author: Adobe Systems Incorporated
Subject: Adobe Portable Document Format (PDF)
Keywords:
Creator: FrameMaker 7.2
Producer: Acrobat Distiller 7.0.5 (Windows)
Created: D:20061017081020Z
Modified: D:20061118211043-02'30'
XMP pdf:Producer: Adobe PDF library 7.77
XMP xmp:CreateDate: 2006-12-21T18:19:09+01:00
XMP xmp:CreatorTool: Adobe Illustrator CS2
XMP xmp:MetadataDate: 2006-12-21T18:19:09Z
XMP xmp:ModifyDate: 2006-12-21T18:19:09Z
XMP dc:title: AI6
```

The details of the format for creation and modification dates can be found in Appendix A.

By default, cpdf strips to ASCII, discarding character codes in excess of 127. In order to preserve the original unicode, add the -utf8 option. To disable all postprocessing of the string, add -raw. See Section 1.17 for more information.

The -page-info operation prints the page label, media box and other boxes page-by-page to standard output, for all pages in the current range.

```
$cpdf -page-info 14psfonts.pdf
Page 1:
Label: i
MediaBox: 0.000000 0.000000 600.000000 450.000000
CropBox: 200.000000 200.000000 500.000000
BleedBox:
```

TrimBox: ArtBox: Rotation: 0

Note that the format for boxes is minimum x, minimum y, maximum x, maximum y.

The -pages operation prints the number of pages in the file.

```
cpdf -pages Archos.pdf
8
```

11.2 Setting Document Information

The *document information dictionary* in a PDF file specifies various pieces of information about a PDF. These can be consulted in a PDF viewer (for instance, Acrobat).

Here is a summary of the commands for setting entries in the document information dictionary:

Information	Example command-line fragment
Title	cpdf -set-title "Discourses"
Author	cpdf -set-author "Joe Smith"
Subject	cpdf -set-subject "Behavior"
Keywords	cpdf -set-keywords "Ape Primate"
Creator	cpdf -set-creator "Original Program"
Producer	cpdf -set-producer "Distilling Program"
Creation Date	cpdf -set-create "D:19970915110347-08'00'"
Modification Date	cpdf -set-modify "D:19970915110347-08'00'"
Mark as Trapped	cpdf -set-trapped
Mark as Untrapped	cpdf -set-untrapped

(The details of the format for creation and modification dates can be found in Appendix A. Using the date "now" uses the time and date at which the command is executed. Note also that -producer and -creator may be used to set the producer and/or the creator when writing any file, separate from the operations described in this chapter.)

For example, to set the title, the full command line would be

cpdf -set-title "A Night in London" in.pdf -o out.pdf

The text string is considered to be in UTF8 format, unless the -raw option is added—in which case, it is unprocessed, save for the replacement of any octal escape sequence such as $\017$, which is replaced by a character of its value (here, 15).

To set also any field in the XMP metadata, add <code>-also-set-xmp</code>. The field must exist already. To set only the field (not the document information dictionary), add <code>-just-set-xmp</code> instead.

11.3 XMP Metadata

PDF files can contain a piece of arbitrary metadata, often in XMP format. This is typically stored in an uncompressed stream, so that other applications can read it without having to decode the whole PDF. To set the metadata:

```
cpdf -set-metadata data.xml in.pdf -o out.pdf
```

To remove any metadata:

cpdf -remove-metadata in.pdf -o out.pdf

To print the current metadata to standard output:

cpdf -print-metadata in.pdf

To create XMP metadata from scratch, using any information in the Document Information Dictionary (old-style metadata):

```
cpdf -create-metadata in.pdf -o out.pdf
```

To set the XMP metadata date field, use:

cpdf -set-metadata-date <date> in.pdf -o out.pdf

The date format is defined in Appendix A.2. Using the date "now" uses the time and date at which the command is executed.

11.4 Upon Opening a Document

11.4.1 Page Layout

The <code>-set-page-layout</code> operation specifies the page layout to be used when a document is opened in, for instance, Acrobat. The possible (case-sensitive) values are:

Chapter 11. Document Information and Metadata

SinglePage	Display one page at a time
OneColumn	Display the pages in one column
TwoColumnLeft	Display the pages in two columns, odd numbered pages on the left
TwoColumnRight	Display the pages in two columns, even numbered pages on the left
TwoPageLeft	(PDF 1.5 and above) Display the pages two at a time, odd numbered pages on the left
TwoPageRight	(PDF 1.5 and above) Display the pages two at a time, even numbered pages on the left

For instance:

cpdf -set-page-layout TwoColumnRight in.pdf -o out.pdf

NB: If the file has a valid /OpenAction setting, which tells the PDF reader to open at a certain page or position on a page, this will override the page layout option. To prevent this, use the -remove-dict-entry functionality from Section 18.9:

cpdf -remove-dict-entry /OpenAction in.pdf -o out.pdf

11.4.2 Page Mode

The *page mode* in a PDF file defines how a viewer should display the document when first opened. The possible (case-sensitive) values are:

UseNone	Neither document outline nor thumbnail images visible
UseOutlines	Document outline (bookmarks) visible
UseThumbs	Thumbnail images visible
FullScreen	Full-screen mode (no menu bar, window controls, or any- thing but the document visible)
UseOC	(PDF 1.5 and above) Optional content group panel visible
UseAttachments	(PDF 1.5 and above) Attachments panel visible

For instance:

cpdf -set-page-mode FullScreen in.pdf -o out.pdf

11.4.3 Display Options

-hide-toolbar	Hide the viewer's toolbar
-hide-menubar	Document outline (bookmarks) visible
-hide-window-ui	Hide the viewer's scroll bars
-fit-window	Resize the document's windows to fit size of first page
-center-window	Position the document window in the center of the screen
-display-doc-title	Display the document title instead of the file name in the title bar

For instance:

cpdf -hide-toolbar true in.pdf -o out.pdf

The page a PDF file opens at can be set using -open-at-page:

cpdf -open-at-page 15 in.pdf -o out.pdf

To have that page scaled to fit the window in the viewer, use <code>-open-at-page-fit</code> instead:

cpdf -open-at-page-fit end in.pdf -o out.pdf

(Here, we used end to open at the last page. Any page specification describing a single page is ok here.)

11.5 Page Labels

It is possible to add *page labels* to a document. These are not the printed on the page, but may be displayed alongside thumbnails or in print dialogue boxes by PDF readers. We use -add-page-labels to do this, by default with decimal arabic numbers (1,2,3...). We can add -label-style to choose what type of labels to add from these kinds:

DecimalArabic	1, 2, 3, 4, 5
LowercaseRoman	i, ii, iii, iv, v
UppercaseRoman	I, II, III, IV, V
LowercaseLetters	a, b, c,, z, aa, bb
UppercaseLetters	A, B, C,, Z, AA, BB
NoLabelPrefixOnly	No number, but a prefix will be used if defined.

We can use *-label-prefix* to add a textual prefix to each label. Consider a file with twenty pages and no current page labels (a PDF reader will assume 1,2,3... if there are none). We will add the following page labels:

i, ii, iii, iv, 1, 2, 3, 4, 5, 6, 7, 8, 9, 10, A-0, A-1, A-2, A-3, A-4, A-5

Here are the commands, in order:

By default the labels begin at page number 1 for each range. To override this, we can use <code>-label-startval</code> (we used 0 in the final command), where we want the numbers to begin at zero rather than one. The option <code>-labels-progress</code> can be added to make sure the start value progresses between sub-ranges when the page range specified is disjoint, e.g 1–9, 30–40 or odd.

Page labels may be removed altogether by using <code>-remove-page-labels</code> command. To print the page labels from an existing file, use <code>-print-page-labels</code>. For example:

```
$ cpdf -print-page-labels cpdfmanual.pdf
labelstyle: LowercaseRoman
labelprefix: None
startpage: 1
startvalue: 1
labelstyle: DecimalArabic
labelprefix: None
startpage: 9
startvalue: 1
```

File Attachments

```
cpdf -attach-file <filename> [-to-page <page number>] in.pdf -o out.pdf
cpdf -list-attached-files in.pdf
cpdf -remove-files in.pdf -o out.pdf
cpdf -dump-attachments in.pdf -o <directory>
```

PDF supports adding attachments (files of any kind, including other PDFs) to an existing file. The cpdf tool supports adding and removing *document-level attachments* — that is, ones which are associated with the document as a whole rather than with an individual page, and also *page-level attachments*, associated with a particular page.

12.1 Adding Attachments

To add an attachment, use the -attach-file operation. For instance,

cpdf -attach-file sheet.xls in.pdf -o out.pdf

attaches the Excel spreadsheet sheet.xls to the input file. If the file already has attachments, the new file is added to their number. You can specify multiple files to be attached by using -attach-file multiple times. They will be attached in the given order.

The -to-page option can be used to specify that the files will be attached to the given page, rather than at the document level. The -to-page option may be specified at most once.

12.2 Listing Attachments

To list all document- and page-level attachments, use the <code>-list-attached-files</code> operation. The page number and filename of each attachment is given, page 0 representing a document-level attachment.

```
$cpdf -list-attached-files 14psfonts.pdf
0 utility.ml
0 utility.mli
4 notes.xls
```

12.3 Removing Attachments

To remove all document-level and page-level attachments from a file, use the <code>-remove-files</code> operation:

```
cpdf -remove-files in.pdf -o out.pdf
```

12.4 Dumping Attachments to File

The <code>-dump-attachments</code> operation, when given a PDF file and a directory path as the output, will write each attachment under its filename (as displayed by <code>-list-attached-files</code> to that directory. The directory must exist prior to the call.

cpdf -dump-attachments in.pdf -o /home/fred/attachments

Unless the -raw option is given, the filenames are stripped of dubious special characters before writing. It is converted from unicode to 7 bit ASCII, and the following characters are removed, in addition to any character with ASCII code less than 32:

/ ? < > \setminus : * | " ^ + =

Working with Images

```
cpdf -extract-images in.pdf [<range>] [-im <path>] [-p2p <path>]
    [-dedup | -dedup-perpage] -o <path>
```

cpdf -image-resolution <minimum resolution> in.pdf [<range>]

13.1 Extracting images

Cpdf can extract the raster images to a given location. JPEG, JPEG2000 and JBIG2 images are extracted directly. Other images are written as PNGs, processed with either ImageMagick's "magick" command, or NetPBM's "pnmtopng" program, whichever is installed.

```
cpdf -extract-images in.pdf [<range>] [-im <path>] [-p2p <path]
        [-dedup | -dedup-perpage] -o <path>
```

The -im or -p2p option is used to give the path to the external tool, one of which must be installed. The output specifer, e.g -o output/%%% gives the number format for numbering the images. Output files are named serially from 0, and include the page number too. For example, output files might be called output/000-p1.jpg, output/001-p1.png, output/002-p3.jpg etc. Here is an example invocation:

cpdf -extract-images in.pdf -im magick -o output/%%%

The output directory must already exist. The -dedup option deduplicates images entirely; the -dedup-perpage option only per page.

13.2 Detecting Low-resolution Images

To list all images in the given range of pages which fall below a given resolution (in dots-perinch), use the -image-resolution function: cpdf -image-resolution 300 in.pdf [<range>]

2, /Im5, 531, 684, 149.935297, 150.138267 2, /Im6, 184, 164, 149.999988, 150.458710 2, /Im7, 171, 156, 149.999996, 150.579145 2, /Im9, 65, 91, 149.999986, 151.071856 2, /Im10, 94, 60, 149.999990, 152.284285 2, /Im15, 184, 139, 149.960011, 150.672060 4, /Im29, 53, 48, 149.970749, 151.616446

The format is *page number, image name, x pixels, y pixels, x resolution, y resolution.* The resolutions refer to the image's effective resolution at point of use (taking account of scaling, rotation etc).

13.3 Removing an Image

To remove a particular image, find its name using <code>-image-resolution</code> with a sufficiently high resolution (so as to list all images), and then apply the <code>-draft</code> and <code>-draft-remove-only</code> operations from Section 18.1.

Fonts

14.1 Listing Fonts

The *-list-fonts* operation prints the fonts in the document, one-per-line to standard output. For example:

```
1 /F245 /Type0 /Cleargothic-Bold /Identity-H
1 /F247 /Type0 /ClearGothicSerialLight /Identity-H
1 /F248 /Type1 /Times-Roman /WinAnsiEncoding
1 /F250 /Type0 /Cleargothic-RegularItalic /Identity-H
2 /F13 /Type0 /Cleargothic-Bold /Identity-H
2 /F16 /Type0 /Arial-ItalicMT /Identity-H
2 /F21 /Type0 /ArialMT /Identity-H
2 /F58 /Type1 /Times-Roman /WinAnsiEncoding
2 /F59 /Type0 /ClearGothicSerialLight /Identity-H
2 /F61 /Type0 /Cleargothic-BoldItalic /Identity-H
2 /F68 /Type0 /Cleargothic-RegularItalic /Identity-H
3 /F47 /Type0 /Cleargothic-Bold /Identity-H
3 /F49 /Type0 /ClearGothicSerialLight /Identity-H
3 /F50 /Type1 /Times-Roman /WinAnsiEncoding
3 /F52 /Type0 /Cleargothic-BoldItalic /Identity-H
```

```
3 /F54 /Type0 /TimesNewRomanPS-BoldItalicMT /Identity-H
3 /F57 /Type0 /Cleargothic-RegularItalic /Identity-H
4 /F449 /Type0 /Cleargothic-Bold /Identity-H
4 /F451 /Type0 /ClearGothicSerialLight /Identity-H
4 /F452 /Type1 /Times-Roman /WinAnsiEncoding
```

The first column gives the page number, the second the internal unique font name, the third the type of font (Type1, TrueType etc), the fourth the PDF font name, the fifth the PDF font encoding.

14.2 Listing characters in a font

We can use cpdf to find out which characters are available in a given font, and to print the map between character codes, unicode codepoints, and Adobe glyph names. This is presently a best-effort service, and does not cover all font/encoding types.

We find the name of the font by using -list-fonts:

```
$ ./cpdf -list-fonts cpdfmanual.pdf 1
1 /F46 /Type1 /XYPLPB+NimbusSanL-Bold
1 /F49 /Type1 /MCBERL+URWPalladioL-Roma
```

We may then print the table, giving either the font's name (e.g /F46) or basename (e.g /XYPLPB+NimbusSanL-Bold):

```
$ ./cpdf -print-font-table /XYPLPB+NimbusSanL-Bold
         -print-font-table-page 1 cpdfmanual.pdf
67 = U+0043 (C - LATIN CAPITAL LETTER C) = /C
68 = U+0044 (D - LATIN CAPITAL LETTER D) = /D
70 = U+0046 (F - LATIN CAPITAL LETTER F) = /F
71 = U+0047 (G - LATIN CAPITAL LETTER G) = /G
76 = U+004C (L - LATIN CAPITAL LETTER L) = /L
80 = U+0050 (P - LATIN CAPITAL LETTER P) = /P
84 = U+0054 (T - LATIN CAPITAL LETTER T) = /T
97 = U+0061 (a - LATIN SMALL LETTER A) = /a
99 = U+0063 (c - LATIN SMALL LETTER C) = /c
100 = U+0064 (d - LATIN SMALL LETTER D) = /d
101 = U+0065 (e - LATIN SMALL LETTER E) = /e
104 = U+0068 (h - LATIN SMALL LETTER H) = /h
105 = U+0069 (i - LATIN SMALL LETTER I) = /i
108 = U+006C (1 - LATIN SMALL LETTER L) = /1
109 = U+006D (m - LATIN SMALL LETTER M) = /m
110 = U+006E (n - LATIN SMALL LETTER N) = /n
111 = U+006F (O - LATIN SMALL LETTER O) = /O
112 = U+0070 (p - LATIN SMALL LETTER P) = /p
114 = U+0072 (r - LATIN SMALL LETTER R) = /r
115 = U+0073 (s - LATIN SMALL LETTER S) = /s
116 = U+0074 (t - LATIN SMALL LETTER T) = /t
```

The first column is the character code, the second the Unicode codepoint, the character itself and its Unicode name, and the third the Adobe glyph name.

14.3 Copying Fonts

In order to use a font other than the standard 14 with <code>-add-text</code>, it must be added to the file. The font source PDF is given, together with the font's resource name on a given page, and that font is copied to all the pages in the input file's range, and then written to the output file.

The font is named in the output file with its basefont name, so it can be easily used with -add-text.

For example, if the file fromfile.pdf has a font /GHLIGA+c128 with the name /F10 on page 1 (this information can be found with -list-fonts), the following would copy the font to the file in.pdf on all pages, writing the output to out.pdf:

```
cpdf -copy-font fromfile.pdf -copy-font-name /F10
        -copy-font-page 1 in.pdf -o out.pdf
```

Text in this font can then be added by giving -font /GHLIGA+c128. Be aware that due to the vagaries of PDF font handling concerning which characters are present in the source font, not all characters may be available, or cpdf may not be able to work out the conversion from UTF8 to the font's own encoding. You may add -raw to the command line to avoid any conversion, but the encoding (mapping from input codes to glyphs) may be non-obvious and require knowledge of the PDF format to divine.

14.4 Removing Fonts

To remove embedded fonts from a document, use <code>-remove-fonts</code>. PDF readers will substitute local fonts for the missing fonts. The use of this function is only recommended when file size is the sole consideration.

```
cpdf -remove-fonts in.pdf -o out.pdf
```

14.5 Missing Fonts

The -missing-fonts operation lists any unembedded fonts in the document, one per line.

```
cpdf -missing-fonts in.pdf
```

The format is

Page number, Name, Subtype, Basefont, Encoding

The operation -embed-missing-fonts will process the file with gs (which must be installed) to embed missing fonts (where found):

cpdf -embed-missing-fonts -gs gs in.pdf -o out.pdf

PDF and JSON

```
cpdf in.pdf -output-json -o out.json
  [-output-json-parse-content-streams]
  [-output-json-no-stream-data]
```

Output PDF as JSON data. Each object is written under its object number. The object number zero is used to store the trailer dictionary. Negative object numbers are reserved for future format expansion. Here is an example of the output for a small PDF:

The option -output-json-parse-content-streams will also convert content streams to JSON, so our example content stream will be expanded:

```
[ [ 1.000000, 0.000000, 0.000000, 1.000000, 50.000000, 770.000000,
        "cm" ],
        [ "BT" ], [ "/F0", 36.000000, "Tf" ], [ "Hello, World!", "Tj" ],
        [ "ET" ] ] ] ]
```

The option <code>-output-json-no-stream-data</code> simply elides the stream data instead, leading to much smaller JSON files.

Optional Content Groups

```
cpdf -ocg-list in.pdf
cpdf -ocg-rename -ocg-rename-from <a> -ocg-rename-to <b> in.pdf -o out.pdf
cpdf -ocg-order-all in.pdf -o out.pdf
cpdf -ocg-coalesce-on-name in.pdf -o out.pdf
```

In a PDF file, optional content groups are used to group graphical elements together, so they may appear or not, depending on the preference of the user. They are similar in some ways to layers in graphics illustration programs.

cpdf -ocg-list in.pdf

List the optional content groups in the PDF, one per line, to standard output.

cpdf -ocg-rename -ocg-rename-from <a> -ocg-rename-to in.pdf -o out.pdf

Rename an optional content group.

```
cpdf -ocg-coalesce-on-name in.pdf -o out.pdf
```

Coalesce optional content groups. For example, if we merge or stamp two files both with an OCG called "Layer 1", we will have two different optional content groups. Running -ocg-coalesce-on-name will merge the two into a single optional content group.

```
cpdf -ocg-order-all in.pdf -o out.pdf
```

Ensure that every optional content group appears in the order list.

Creating New PDFs

```
cpdf -create-pdf [-create-pdf-pages <n>]
    [-create-pdf-papersize <paper size>] -o out.pdf
cpdf -typeset <text file> [-create-pdf-papersize <size>]
    [-font <font>] [-font-size <size>] -o out.pdf
```

17.1 A new blank PDF

We can build a new PDF file, given a number of pages and a paper size. The default is one page, A4 portrait.

```
cpdf -create-pdf -create-pdf-pages 20
-create-pdf-papersize usletterportrait -o out.pdf
```

The standard paper sizes are listed in Section 3.1, or you may specify the width and height directly, as described in the same chapter.

17.2 Convert a text file to PDF

A basic text to PDF convertor is included in cpdf. It takes a UTF8 text file (ASCII is a subset of UTF8) and typesets it ragged-right, splitting on whitespace. Both Windows and Unix line endings are allowed.

```
cpdf -typeset file.txt -create-pdf-papersize a3portrait
        -font Courier -font-size 10 -o out.pdf
```

The standard paper sizes are listed in Section 3.1, or you may specify the width and height directly, as described in the same chapter. The standard fonts are listed in chapter 8. The default font is TimesRoman and the default size is 12.

Miscellaneous

```
cpdf -draft [-boxes] [-draft-remove-only <n>] in.pdf [<range>] -o out.pdf
cpdf -remove-all-text in.pdf [<range>] -o out.pdf
cpdf -blacktext in.pdf [<range>] -o out.pdf
cpdf -blacklines in.pdf [<range>] -o out.pdf
cpdf -blackfills in.pdf [<range>] -o out.pdf
cpdf -thinlines <minimum thickness> in.pdf [<range>] -o out.pdf
cpdf -clean in.pdf -o out.pdf
cpdf -set-version <version number> in.pdf -o out.pdf
cpdf -copy-id-from source.pdf in.pdf -o out.pdf
cpdf -remove-id in.pdf -o out.pdf
cpdf -list-spot-colors in.pdf
cpdf -print-dict-entry <key> in.pdf
cpdf -remove-dict-entry <key> [-dict-entry-search <term>]
      in.pdf -o out.pdf
cpdf -replace-dict-entry <key> -replace-dict-entry-value <value>
     [-dict-entry-search <term>] in.pdf -o out.pdf
cpdf -remove-clipping [<range>] in.pdf -o out.pdf
```

18.1 Draft Documents

The -draft operation removes bitmap (photographic) images from a file, so that it can be printed with less ink. Optionally, the -boxes option can be added, filling the spaces left blank with a crossed box denoting where the image was. This is not guaranteed to be fully visible in all cases (the bitmap may be have been partially covered by vector objects or clipped in the original). For example:

```
cpdf -draft -boxes in.pdf -o out.pdf
```

To remove a single image only, specify -draft-remove-only, giving the name of the image obtained by a call to -image-resolution as described in Section 13.2 and giving the appropriate page. For example:

```
cpdf -draft -boxes -draft-remove-only "/Im1" in.pdf 7 -o out.pdf
```

To remove text instead of images, use the -remove-all-text operation:

```
cpdf -remove-all-text in.pdf -o out.pdf
```

18.2 Blackening Text, Lines and Fills

Sometimes PDF output from an application (for instance, a web browser) has text in colors which would not print well on a grayscale printer. The -blacktext operation blackens all text on the given pages so it will be readable when printed.

This will not work on text which has been converted to outlines, nor on text which is part of a form.

```
cpdf -blacktext in.pdf -o out.pdf
```

The -blacklines operation blackens all lines on the given pages.

cpdf -blacklines in.pdf -o out.pdf

The -blackfills operation blackens all fills on the given pages.

cpdf -blackfills in.pdf -o out.pdf

Contrary to their names, all these operations can use another color, if specified with -color.

18.3 Hairline Removal

Quite often, applications will use very thin lines, or even the value of 0, which in PDF means "The thinnest possible line on the output device". This might be fine for on-screen work, but when printed on a high resolution device, such as by a commercial printer, they may be too faint, or disappear altogether. The -thinlines operation prevents this by changing all lines thinner than <minimal thickness> to the given thickness. For example:

cpdf -thinlines 0.2mm in.pdf [<range>] -o out.pdf

Thicken all lines less than 0.2mm to that value.

18.4 Garbage Collection

Sometimes incremental updates to a file by an application, or bad applications can leave data in a PDF file which is no longer used. This function removes that unneeded data.

```
cpdf -clean in.pdf -o out.pdf
```

18.5 Change PDF Version Number

To change the pdf version number, use the <code>-set-version</code> operation, giving the part of the version number after the decimal point. For example:

```
cpdf -set-version 4 in.pdf -o out.pdf
```

Change file to PDF 1.4.

This does not alter any of the actual data in the file — just the supposed version number. For PDF versions starting with 2 add ten to the number. For example, for PDF version 2.0, use -set-version 10.

18.6 Copy ID

The *-copy-id-from* operation copies the ID from the given file to the input, writing to the output.

```
cpdf -copy-id-from source.pdf in.pdf -o out.pdf
```

Copy the id from source.pdf to the contents of in.pdf, writing to out.pdf.

If there is no ID in the source file, the existing ID is retained. You cannot use <code>-recrypt</code> with <code>-copy-id-from</code>.

18.7 Remove ID

The -remove-id operation removes the ID from a document.

cpdf -remove-id in.pdf -o out.pdf

Remove the ID from in.pdf, writing to out.pdf.

You cannot use -recrypt with -remove-id.

18.8 List Spot Colours

This operation lists the name of any "separation" color space in the given PDF file.

```
cpdf -list-spot-colors in.pdf
```

List the spot colors, one per line in in.pdf, writing to stdout.

18.9 PDF Dictionary Entries

This is for editing data within the PDF's internal representation. Use with caution. To print a dictionary entry:

cpdf -print-dict-entry /URI in.pdf -o out.pdf

Print all URLs in annotation hyperlinks in.pdf.

To remove a dictionary entry:

cpdf -remove-dict-entry /One in.pdf -o out.pdf

Remove the entry for /One in every dictionary in.pdf, writing to out.pdf.

```
cpdf -remove-dict-entry /One -dict-entry-search "1" in.pdf -o out.pdf
```

Replace the entry for /One in every dictionary in.pdf if the key's value is the given value, writing to out.pdf.

To replace a dictionary entry:

Remove the entry for /One in every dictionary in.pdf if the key's value is the given value, writing to out.pdf.

18.10 Removing Clipping

The -remove-clipping operation removes any clipping paths on given pages from the file.

```
cpdf -remove-clipping in.pdf -o out.pdf
```

Remove clipping paths in in.pdf, writing to out.pdf.

Appendix A

Dates

A.1 PDF Date Format

Dates in PDF are specified according to the following format:

D:YYYYMMDDHHmmSSOHH'mm'

where:

- YYYY is the year;
- MM is the month;
- DD is the day (01-31);
- HH is the hour (00-23);
- mm is the minute (00-59);
- SS is the second (00-59);
- 0 is the relationship of local time to Universal Time (UT), denoted by '+', '-' or 'Z';
- HH is the absolute value of the offset from UT in hours (00-23);
- mm is the absolute value of the offset from UT in minutes (00-59).

A contiguous prefix of the parts above can be used instead, for lower accuracy dates. For example:

D:2014 (2014) D:20140103 (3rd January 2014) D:201401031854-08'00' (3rd January 2014, 6:54PM, US Pacific Standard Time)

A.2 XMP Metadata Date Format

These are the possible data formats for -set-metadata-date:

```
YYYY
YYYY-MM
YYYY-MM-DD
YYYY-MM-DDThh:mmTZD
YYYY-MM-DDThh:mm:ssTZD
```

where:

YYYY	year
MM	month ($01 = Jan$)
DD	day of month (01 to 31)
hh	hour (00 to 23)
mm	minute (00 to 59)

- ss second (00 to 59)
- TZD time zone designator (Z or +hh:mm or -hh::mm)

Index

AND, 5 annotations copying, 45 listing, 45 removing, 46 attachments, 55 adding, 55 dumping to file, 56 listing, 55 removing, 56 bates numbers, 35 blacken fills, 70 lines, 70 text, 70 blank pages inserting, 41 bookmarks, 25 adding, 27 listing, 25 opening at level, 28 removing, 27 color, 37 compressing, 23 control file, 9 Create, 67 create new PDF, 67 creator, 5 crop pages, 18 date, 34 defined, 75 decompressing, 23 decryption, 3, 21 document information, 47 document outline, 25

draft, 69 encryption, 13, 21 error handling, 9 file ID, 6 copy, 71 remove, 71 flip pages, 18 font, 36 embedding, 10 listing, 59 garbage collection, 71 hairline removal, 70 input files, 1 input range, 2 **JSON**, 63 linearization, 6 malformed file, 8 media box, 18 merging, 11 metadata, 47 XMP, 50 object stream, 7 **Optional Content Group**, 65 outline text, 38 output files, 1 owner password, 3 page labels, 52 layout, 50

mode, 51 numbers, 34 range, 2 size, 16 password, 3 presentations, 31 printer's marks, 19 producer, 5 range, 2 removing text, 34 reversing, 2 rotate contents, 18 pages, 17 scale pages, 16 shift page contents, 17 splitting, 12 on bookmarks, 12 spot colour, 72 squeeze, 24 stamp text, 34 standard input, 4 standard output, 4 text encodings, 10 time, 34 trim marks, 19 two-up, imposition, impose, 42 units, 5 user password, 3 version number, 6, 71 watermarks, 33 XMP metadata, 50