# Coherent PDF Command Line Toolkit

User Manual Version 2.2 (March 2017)

**Coherent Graphics Ltd** 

For bug reports, feature requests and comments, email contact@coherentgraphics.co.uk

©2017 Coherent Graphics Limited. All rights reserved. ISBN 978-0957671140

Adobe, Acrobat, Adobe PDF, Adobe Reader and PostScript are registered trademarks of Adobe Systems Incorporated. Windows, Powerpoint and Excel are registered trademarks of Microsoft Corporation.

# Contents

1	Basi	sic Usage 1		
	1.1	Input and Output Files	1	
	1.2	Input Ranges	2	
	1.3	Working with Encrypted Documents	3	
	1.4	Standard Input and Standard Output	3	
	1.5	Doing Several Things at Once with AND	3	
	1.6	Units	4	
	1.7	Setting the Producer and Creator	4	
	1.8	PDF Version Numbers	5	
	1.9	File IDs	5	
	1.10	Linearization	5	
	1.11	Object Streams	6	
	1.12	Malformed Files	6	
	1.13	Error Handling	7	
	1.14	Control Files	7	
	1.15	String Arguments	7	
	1.16	Text Encodings	8	
	1.17	Font Embedding	8	
2 Merging and Splitting			9	
	2.1	Merging	9	
	2.2		9	
	2.3	. 0	10	

# **Typographical Conventions**

Command lines to be typed are shown in typewriter font in a box. For example:

cpdf in.pdf -o out.pdf

When describing the general form of a command, rather than a particular example, square brackets [] are used to enclose optional parts, and angled braces <> to enclose general descriptions which may be substituted for particular instances. For example,

cpdf <operation> in.pdf [<range>] -o out.pdf

describes a command line which requires an operation and, optionally, a range. An exception is that we use in.pdf and out.pdf instead of <input file> and <output file> to reduce verbosity. Under Microsoft Windows, type cpdf.exe instead of cpdf.

### Chapter 1

## **Basic** Usage

-0	-idir 〈directory〉	-recrypt
-stdout	-stdin	-stdin-user <password></password>
-stdin-owner <password></password>	-producer <text></text>	-creator <text></text>
-change-id	-1	-cpdflin (filename)
-keep-l	-no-preserve-objstm	-create-objstm
-control (filename)	-args <filename></filename>	-utf8
-stripped	-raw	-no-embed-font

The Coherent PDF tools provide a wide range of facilities for modifying PDF files created by other means. There is a single command-line program cpdf (cpdf.exe under Microsoft Windows). The rest of this manual describes the options that may be given to this program.

#### 1.1 Input and Output Files

The typical pattern for usage is

<pre>cpdf [<operation>] <input file(s)=""/> -o <output file=""></output></operation></pre>			
and the simplest concrete example, assuming the existence of a file in.pdf is:			
cpdf in.pdf -o out.pdf			

which copies in.pdf to out.pdf. The input and output may be the same file. Of course, we should like to do more interesting things to the PDF file than that!

Files on the command line are distinguished from other input by their containing a period. If an input file does not contain a period, it should be preceded by -i. For example:

cpdf -i in -o out.pdf

A whole directory of files may be added (where a command supports multiple files) by using the -idir option:

cpdf -merge -idir myfiles -o out.pdf

The files in the directory myfiles are considered in alphabetical order. They must all be PDF files. If the names of the files are numeric, leading zeroes will be required for the order to be correct (e.g 001.pdf, 002.pdf etc).

#### 1.2 Input Ranges

An *input range* may be specified after each input file. This is treated differently by each operation. For instance

cpdf in.pdf 2-5 out.pdf

extracts pages two, three, four and five from in.pdf, writing the result to out.pdf, assuming that in.pdf contains at least five pages. Here are the rules for building input ranges:

- A dash (-) defines ranges, e.g. 1-5 or 6-3.
- A comma (,) allows one to specify several ranges, e.g. 1-2,4-5.
- The word end represents the last page number.
- The words odd and even can be used in place of or at the end of a page range to restrict to just the odd or even pages.
- The words **portrait** and **landscape** can be used in place of or at the end of a page range to restrict to just those pages which are portrait or landscape. Note that the meaning of "portrait" and "landscape" does not take account of any viewing rotation in place (use **-upright** first, if required). A page with equal width and height is considered neither portrait nor landscape.
- The word reverse is the same as end-1.
- The word all is the same as 1-end.
- A range must contain no spaces.
- A tilde (~) defines a page number counting from the end of the document rather than the beginning. Page ~1 is the last page, ~2 the penultimate page etc.

For example:

cpdf in.pdf 1,2,7-end -o out.pdf
Remove pages three, four, five and six from a document.
cpdf in.pdf 1-16odd -o out.pdf
Extract the odd pages 1,3,...,13,15.
cpdf in.pdf landscape -rotate 90 -o out.pdf
Rotate all landscape pages by ninety degrees.
cpdf in.pdf 1,all -o out.pdf
Duplicate the front page of a document, perhaps as a fax cover sheet.
cpdf in.pdf 3- 1 -o out.pdf
Extract the last three pages of a document, in order.

#### **1.3** Working with Encrypted Documents

In order to perform many operations, encrypted input PDF files must be decrypted. Some require the owner password, some either the user or owner passwords. Either password is supplied by writing user=<password> or owner=<password> following each input file requiring it (before or after any range). The document will *not* be re-encrypted upon writing. For example:

```
cpdf in.pdf user=charles -info
```

```
cpdf in.pdf owner=fred reverse -o out.pdf
```

To re-encrypt the file with its existing encryption upon writing, which is required if only the user password was supplied, but allowed in any case, add the **-recrypt** option:

cpdf in.pdf user=fred reverse -recrypt -o out.pdf

The password required (owner or user) depends upon the operation being performed. Separate facilities are provided to decrypt and encrypt files (See Section ??).

#### 1.4 Standard Input and Standard Output

Thus far, we have assumed that the input PDF will be read from a file on disk, and the output written similarly. Often it's useful to be able to read input from stdin (Standard Input) or write output to stdout (Standard Output) instead. The typical use is to join several programs together into a *pipe*, passing data from one to the next without the use of intermediate files. Use -stdin to read from standard input, and -stdout to write to standard input, either to pipe data between multiple programs, or multiple invocations of the same program. For example, this sequence of commands (all typed on one line)

```
cpdf in.pdf reverse -stdout |
cpdf -stdin 1-5 -stdout |
cpdf -stdin reverse -o out.pdf
```

extracts the last five pages of in.pdf in the correct order, writing them to out.pdf. It does this by reversing the input, taking the first five pages and then reversing the result.

To supply passwords for a file from -stdin, use -stdin-owner <password> and/or -stdin-user <password>.

Using -stdout on the final command in the pipeline to output the PDF to screen is not recommended, since PDF files often contain compressed sections which are not screen-readable.

Several cpdf operations write to standard output by default (for example, listing fonts). A useful feature of the command line (not specific to cpdf) is the ability to redirect this output to a file. This is achieved with the > operator:

```
cpdf -info in.pdf > file.txt
```

Use the -info operation (See Section ??), redirecting the output to file.txt.

#### 1.5 Doing Several Things at Once with AND

The keyword AND can be used to string together several commands in one. The advantage compared with using pipes is that the file need not be repeatedly parsed and written out, saving time.

To use AND, simply leave off the output specifier (e.g -o) of one command, and the input specifier (e.g filename) of the next. For instance:

```
cpdf -merge in.pdf in2.pdf AND -add-text "Label"
AND -merge in3.pdf -o out.pdf
Merge in.pdf and in2.pdf together, add text to both pages, append in3.pdf and write to out.pdf.
To specify the range for each section, use -range:
cpdf -merge in.pdf in2.pdf AND -range 2-4 -add-text "Label"
```

AND -merge in3.pdf -o out.pdf

#### 1.6 Units

When measurements are given to cpdf, they are in points (1 point = 1/72 inch). They may optionally be followed by some letters to change the measurement. The following are supported:

- pt Points (72 points per inch). The default.
- cm Centimeters
- mm Millimeters
- in Inches

For example, one may write 14mm or 21.6in. In addition, the following letters stand, in some operations (-scale-page, -scale-to-fit, -scale-contents, -shift, -mediabox, -crop) for various page dimensions:

PW	Page width
PH	Page height
PMINX	Page minimum x coordinate
PMINY	Page minimum y coordinate
PMAXX	Page maximum x coordinate
PMAXY	Page maximum y coordinate
CW	Crop box width
CH	Crop box height
CMINX	Crop box minimum x coordinate
CMINY	Crop box minimum y coordinate
CMAXX	Crop box maximum x coordinate
CMAXY	Crop box maximum y coordinate

For example, we may write PMINX PMINY to stand for the coordinate of the lower left corner of the page.

Simple arithmetic may be performed using the words add, sub, mul and div to stand for addition, subtraction, multiplication and division. For example, one may write 14in sub 30pt or PMINX mul 2

#### 1.7 Setting the Producer and Creator

The -producer and -creator options may be added to any cpdf command line to set the producer and/or creator of the PDF file. If the file was converted from another format, the *creator* is the program producing the original, the *producer* the program converting it to PDF.

cpdf -merge in.pdf in2.pdf -producer MyMerger -o out.pdf

Merge in.pdf and in2.pf, setting the producer to MyMerger and writing the output to out.pdf.

#### 1.8 PDF Version Numbers

When an operation which uses a part of the PDF standard which was introduced in a later version than that of the input file, the PDF version in the output file is set to the later version (most PDF viewers will try to load any PDF file, even if it is marked with a later version number). However, this automatic version changing may be suppressed with the **-keep-version** flag.

Here is a list of Acrobat versions together with the maximum PDF version they are intended to support:

 PDF 1.2
 Acrobat 3.0

 PDF 1.3
 Acrobat 4.0

 PDF 1.4
 Acrobat 5.0

 PDF 1.5
 Acrobat 6.0

 PDF 1.6
 Acrobat 7.0

 PDF 1.7
 Acrobat 8.0, 9.0, 10.0

If you wish to manually alter the PDF version of a file, use the **-set-version** option described in Section **??**.

#### 1.9 File IDs

PDF files contain an ID (consisting of two parts), used by some workflow systems to uniquely identify a file. To change the ID, behavior, use the **-change-id** operation. This will create a new ID for the output file.

```
cpdf -change-id in.pdf -o out.pdf
```

Write in.pdf to out.pdf, changing the ID.

#### 1.10 Linearization

Linearized PDF is a version of the PDF format in which the data is held in a special manner to allow content to be fetched only when needed. This means viewing a multipage PDF over a slow connection is more responsive. By default, cpdf does not linearize output files. To make it do so, add the -1 option to the command line, in addition to any other command being used. For example:

```
cpdf -change-id in.pdf -o out.pdf
cpdf -l in.pdf -o out.pdf
```

Linearize the file in.pdf, writing to out.pdf.

This requires the existence of the external program cpdflin which is provided with commercial versions of cpdf. This must be installed as described in the installation documentation provided with your copy of cpdf. If you are unable to install cpdflin, you must use -cpdflin to let cpdf know where to find it:

```
cpdf.exe -cpdflin "C:\\cpdflin.exe" -l in.pdf -o out.pdf
```

Linearize the file in.pdf, writing to out.pdf.

In extremis, you may place cpdflin and its resources in the current working directory, though this is not recommended. For further help, refer to the installation instructions for your copy of cpdf.

To keep the existing linearization status of a file (produce linearized output if the input is linearized and the reverse), use -keep-l instead of -l.

#### 1.11 Object Streams

PDF 1.5 introduced a new mechanism for storing objects to save space: object streams. by default, cpdf will preserve object streams in input files, creating no more. To prevent the retention of existing object streams, use -no-preserve-objstm:

cpdf -no-preserve-objstm in.pdf -o out.pdf

Write the file in.pdf to out.pdf, removing any object streams.

To create new object streams if none exist, or augment the existing ones, use -create-objstm:

cpdf -create-objstm in.pdf -o out.pdf

Write the file in.pdf to out.pdf, preserving any existing object streams, and creating any new ones for new objects which have been added.

To create wholly new object streams, use both options together:

cpdf -create-objstm -no-preserve-objstm in.pdf -o out.pdf

Write the file in.pdf to out.pdf with wholly new object streams.

Files written with object streams will be set to PDF 1.5 or higher, unless -keep-version is used (see above).

#### 1.12 Malformed Files

There are many malformed PDF files in existence, including many produced by otherwise-reputable applications. cpdf attempts to correct these problems silently.

Grossly malformed files will be reconstructed. The reconstruction progress is shown on stderr (Standard Error):

```
./cpdf in.pdf -o out.pdf
couldn't lex object number
Attempting to reconstruct the malformed pdf in.pdf...
Read 5530 objects
Malformed PDF reconstruction succeeded!
```

Sometimes files can be technically well-formed but use inefficient PDF constructs. If you are sure the input files you are using are impeccably formed, the **-fast** option added to the command line (or, if using AND, to each section of the command line). This will use certain shortcuts which speed up processing, but would fail on badly-produced files.

The **-fast** option may be used with:

Chapter ?? -rotate-contents -upright -vflip -hflip -shift -scale -scale-to-fit -scale-contents Chapter ?? -add-text -stamp-on -stamp-under -combine-pages

If problems occur, refrain from using -fast.

#### 1.13 Error Handling

When cpdf encounters an error, it exits with code 2. An error message is displayed on stderr (Standard Error). In normal usage, this means it's displayed on the screen. When a bad or inappropriate password is given, the exit code is 1.

#### 1.14 Control Files

```
Chapter ??
cpdf -control <filename>
cpdf -args <filename>
```

Some operating systems have a limit on the length of a command line. To circumvent this, or simply for reasons of flexibility, a control file may be specified from which arguments are drawn. This file does not support the full syntax of the command line. Commands are separated by whitespace, quotation marks may be used if an argument contains a space, and the sequence  $\$  may be used to introduce a genuine quotation mark in such an argument.

Several -control arguments may be specified, and may be mixed in with conventional command-line arguments. The commands in each control file are considered in the order in which they are given, after all conventional arguments have been processed. It is recommended to use -args in all new applications. However, -control will be supported for legacy applications.

To avoid interference between -control and AND, a new mechanism has been added. Using -args in place of -control will perform direct textual substitution of the file into the command line, prior to any other processing.

#### 1.15 String Arguments

Command lines are handled differently on each operating system. Some characters are reserved with special meanings, even when they occur inside quoted string arguments. To avoid this problem, cpdf performs processing on string arguments as they are read.

A backslash is used to indicate that a character which would otherwise be treated specially by the command line interpreter is to be treated literally. For example, Unix-like systems attribute a special meaning to the exclamation mark, so the command line

cpdf -add-text "Hello!" in.pdf -o out.pdf		
would fail. We must escape the exclamation mark with a backslash:		
cpdf -add-text "Hello\!" in.pdf -o out.pdf		

It follows that backslashes intended to be taken literally must themselves be escaped (i.e. written  $\backslash \backslash$ ).

#### 1.16 Text Encodings

Some cpdf commands write text to standard output, or read text from the command line or configuration files. These are:

```
-info

-list-bookmarks

-set-author et al.

-list-annotations

There are three options to control how the text is interpreted:

-utf8

-stripped

-raw
```

Add -utf8 to use Unicode UTF8, -stripped to convert to 7 bit ASCII by dropping any high characters, or -raw to perform no processing. The default is -stripped.

### 1.17 Font Embedding

Use the -no-embed-font to avoid embedding the Standard 14 Font metrics when adding text with -add-text.

### Chapter 2

## Merging and Splitting

cpdf -merge in1.pdf [<range>] in2.pdf [<range>] [<more names/ranges>]
[-retain-numbering] [-remove-duplicate-fonts] -o out.pdf
cpdf -split in.pdf -o <format> [-chunk <chunksize>]
cpdf -split-bookmarks <level> in.pdf -o <format>

#### 2.1 Merging

The **-merge** operation allow the merging of several files into one. Ranges can be used to select only a subset of pages from each input file in the output. The output file consists of the concatenation of all the input pages in the order specified on the command line. Actually, the **-merge** can be omitted, since this is the default operation of cpdf.

cpdf -merge a.pdf 1 b.pdf 2-end -o out.pdf

Take page one of a.pdf and all but the first page of b.pdf, merge them and produce out.pdf.

Merge maintains bookmarks, named destinations, and name dictionaries.

Forms and other objects which cannot be merged are retained if they are from the document which first exhibits that feature.

The **-retain-numbering** option keeps the PDF page numbering labels of each document intact, rather than renumbering the output pages from 1.

The **-remove-duplicate-fonts** ensures that fonts used in more than one of the inputs only appear once in the output.

#### 2.2 Splitting

The **-split** operation splits a PDF file into a number of parts which are written to file, their names being generated from a *format*. The optional **-chunk** option allows the number of pages written to each output file to be set.

cpdf -split a.pdf -o out%%%.pdf

Split a.pdf to the files out001.pdf, out002.pdf etc.

cpdf -split a.pdf 1 even -chunk 10 -o dir/out%%%.pdf

Split the even pages of a.pdf to the files out001.pdf, out002.pdf etc. with at most ten pages in each file. The directory (folder) dir must exist.

If the output format does not provide enough numbers for the files generated, the result is unspecified. The following format operators may be used:

- %, %%, %%% etc. Sequence number padded to the number of percent signs
  - **@F** Original filename without extension
  - **QN** Sequence number without padding zeroes
  - **©S** Start page of this chunk
  - **@E** End page of this chunk
  - **@B** Bookmark name at this page

#### 2.3 Splitting on Bookmarks

The -split-bookmarks <level> operation splits a PDF file into a number of parts, according to the page ranges implied by the document's bookmarks. These parts are then written to file with names generated from the given format.

Level 0 denotes the top-level bookmarks, level 1 the next level (sub-bookmarks) and so on. So -split-bookmarks 1 creates breaks on level 0 and level 1 boundaries.

```
cpdf -split-bookmarks 0 a.pdf -o out%%%.pdf
```

Split a.pdf to the files out001.pdf, out002.pdf on bookmark boundaries.

Now, there may be many bookmarks on a single page (for instance, if paragraphs are bookmarked or there are two subsections on one page). The splits calculated by -split-bookmarks ensure that each page appears in only one of the output files. It is possible to use the **@** operators above, including operator **@B** which expands to the text of the bookmark:

cpdf -split-bookmarks 0 a.pdf -o @B.pdf

Split a.pdf on bookmark boundaries, using the bookmark text as the filename.

The bookmark text used for a name is converted from unicode to 7 bit ASCII, and the following characters are removed, in addition to any character with ASCII code less than 32:

/ ? 〈 〉 ∖ % : \* | " ^ + =